Observability Day
NORTH AMERICA

November 12, 2024 Salt Lake City



Jamie DanielsonSoftware Engineer at Honeycomb
Maintainer on OpenTelemetry JS





North America 2024

Measure What Matters

Jamie Danielson, Honeycomb





Jamie Danielson

Software Engineer at Honeycomb Maintainer on OpenTelemetry JS







Agenda

- Reduce the noise
- Customize instrumentation
- Set SLOs for actionable insights





Nuisance alerts

Alert: High CPU Usage

Alert: ... other team's service

If you wait until a customer reports a problem before acting... why have these alerts at all?



Cost of alert fatigue

- Distraction, lowered team morale, increased stress
- You may neglect to investigate an actual failure scenario because you're ignoring the signs




"...instead of counting outages and alerts, we should focus on whether we react to them in a useful manner"

- Fred Hebert, <u>Tracking on-call health</u>



Prioritize actionable alerts





Prioritize actionable alerts

• If the current value being measured does not give enough useful information to start investigating... find another value.



Prioritize actionable alerts

"Failures that get automatically remediated should not trigger alarms."

- Liz Fong-Jones, Observability Engineering

In the case of a self-healing system, failures automatically remediated shouldn't trigger alarms but instead create tickets for business-hour review.






Default metrics aren't enough

- Averages can be misleading
- Spikes in resources may not represent user impact
- Simple metrics do not provide enough information to debug





50th, 85th, 95th, and 99th percentile latencies for a system. From Google SRE book



OpenTelemetry

OpenTelemetry is a standardized way to instrument, generate, collect, and export telemetry data.






Auto-instrumentation with tracing can get you started

- You can get tracing from Service A to Service B
- But you need to trace further logic within Service B if it turns out to be too high level





What happened in here?



```
const getUserHistory = async (username: string) => {
  const id = getUserId(username);
  const response: UserInfo = JSON.parse(
    (await makeRequest(`${userServiceUrl}/${id}`)) as string,
  );
 trace.getActiveSpan().setAttribute(USERID_ATTRIBUTE, response.id);
 await tracer.startActiveSpan('calculate-user-intent', async (span) => {
    await calculateUserIntent();
    span.end();
  }):
  return id;
```







Context-specific attributes

- Geographical information
- Logged in vs anonymous users
- Device type and screen size
- App version in use
- Feature flag enabled
- Discount applied
- ...anything else that might be useful

You don't know what will be different the next time a failure mode occurs.



Context-specific attributes about the state of the app

- App version in use
- Feature flag enabled
- Discount applied

You don't know what will be different the next time a failure mode occurs.



Set up SLOs



What is an SLO?

- SLO: Service Level Objective
 - a goal for measuring service health, or a reliability target
- SLI: Service Level Indicator
 - a specific measurement to define service health

Example SLI: Checkout page loads in 2 seconds

Example SLO: That SLI is true 99.5% of the time



Setting realistic, impactful SLOs

- Do not aim for perfect. 100% is not admirable; it is unrealistic.
- Tie SLOs back to business impact
 - Different SLOs may be needed for different scenarios
- For non-critical signals, create a task to investigate during business hours
 - If user impact is minimal or non-existent, do not page.



"The goal of an SLO is to provide a useful signal: if including a specific datapoint dilutes the signal, then it may be worth excluding them or creating a different measure for them."

- Quail, SRE at Honeycomb



Setting realistic, impactful SLOs

Remember that Refinery alert I talked about earlier?

We realized we had another attribute that more reliably indicated a problem with the service itself, called stress_level.

We now use that in an SLO, and only page if there was a sharp increase in stress_level over a short period of time.



Revisit and refine over time

- Happiness Observability is a journey, not a destination.
- Newer business requirements may mean changes to SLOs
- Check in with your team and run retros on recent incidents.



"Things we find and hear nothing about means we may be sensitive enough (or maybe over-sensitive); things we find and hear about means we're seeing their pain (and maybe not seeing it early enough); things we don't find but customers do are a sign we may have under-sensitive signals."

- Fred Hebert, <u>Alerts are Fundamentally Messy</u>

Find problems before your customers do.



Recap

- Reduce the noise
- Customize instrumentation
- Set SLOs for actionable insights



Resources

- Observability Engineering
- Google SRE Book
- Tracking on-call health
- Alerts are fundamentally messy



Thank you!

Jamie Danielson, Honeycomb

Say hi to our team in the lobby and pick up some stickers and pins!

feedback, slides (soon)

