Nama : Aldo Brian Granada

NIM : L200170182

Kelas : D

Laporan Praktikum
Jaringan Komputer

Tugas Modul 11



Konfigurasi Router Jarkom

```
Router>en
Router#conf term
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int fa /0
                      ^
% Invalid input detected at '^' marker.

Router(config)#int fa 0/0
Router(config-if)#ip address 172.16.0.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#int fa 1/0
Router(config-if)#ip address 172.15.0.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

Router(config-if)#ex
Router(config)#hostname jarkom
jarkom(config)#
```

Konfigurasi Router RPL

```
Router>en
Router#conf term
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#int fa 0/0
Router(config-if)#ip address 172.18.0.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

Router(config-if)#int fa 1/0
Router(config-if)#ip address 172.15.0.3 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0,
changed state to up

Router(config-if)#
```

Konfigurasi Router SI

```
Router>en
Router#conf term
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname SI
SI(config)#int fa 0/0
SI(config-if)#ip address 172.17.0.1 255.255.255.0
SI(config-if)#no shutdown

SI(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

SI(config-if)#int fa 1/0
SI(config-if)#ip address 172.15.0.2 255.255.255.0
SI(config-if)#no shutdown

SI(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0,
changed state to up

SI(config-if)#
```

Konfigurasi Router Gateway

```
Router>en
Router#conf term
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#hostname UMS
UMS(config)#int fa 0/0
UMS(config-if)#ip address 172.19.0.1 255.255.255.0
UMS(config-if)#no shutdown

UMS(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0,
changed state to up

UMS(config-if)#int fa 1/0
UMS(config-if)#ip address 172.15.0.4 255.255.255.0
UMS(config-if)#no shutdown

UMS(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0,
changed state to up

UMS(config-if)#
```

Konfigurasi PC Jarkom



Konfigurasi PC RPL



Konfigurasi PC SI



Konfigurasi PC Admin



Routing Router Jarkom

```
jarkom>en
jarkom#conf term
Enter configuration commands, one per line.  End with CNTL/Z.
jarkom(config)#ip route 172.18.0.0 255.255.255.0 172.15.0.3
jarkom(config)#ip route 172.17.0.0 255.255.255.0 172.15.0.2
jarkom(config)#ip route 172.19.0.0 255.255.255.0 172.15.0.4
jarkom(config)#
```

Routing Router RPL

```
RPL(config)#ip route 172.16.0.0 255.255.255.0 172.15.0.1
RPL(config)#ip route 172.17.0.0 255.255.255.0 172.15.0.2
RPL(config)#ip route 172.19.0.0 255.255.255.0 172.15.0.4
RPL(config)#
```

Routing Router SI

```
SI>en
SI#conf term
Enter configuration commands, one per line.  End with CNTL/Z.
SI(config)#ip route 172.16.0.0 255.255.255.0 172.15.0.1
SI(config)#ip route 172.18.0.0 255.255.255.0 172.15.0.3
SI(config)#ip route 172.19.0.0 255.255.255.0 172.15.0.4
```

Routing Router Gateway

```
UMS(config)#ip route 172.16.0.0 255.255.255.0 172.15.0.1
UMS(config)#ip route 172.18.0.0 255.255.255.0 172.15.0.3
UMS(config)#ip route 172.17.0.0 255.255.255.0 172.15.0.2
UMS(config)#
```

Tes koneksi

```
Pinging 172.16.0.2 with 32 bytes of data:

Reply from 172.16.0.2: bytes=32 time<1ms TTL=126
Reply from 172.16.0.2: bytes=32 time=10ms TTL=126
Reply from 172.16.0.2: bytes=32 time=16ms TTL=126
Reply from 172.16.0.2: bytes=32 time=11ms TTL=126

Ping statistics for 172.16.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 16ms, Average = 9ms

C:\>ping 172.17.0.2

Pinging 172.17.0.2 with 32 bytes of data:

Reply from 172.17.0.2: bytes=32 time=1ms TTL=126
Reply from 172.17.0.2: bytes=32 time<1ms TTL=126
Reply from 172.17.0.2: bytes=32 time=4ms TTL=126
Reply from 172.17.0.2: bytes=32 time=12ms TTL=126

Ping statistics for 172.17.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 12ms, Average = 4ms

C:\>ping 172.18.0.2

Pinging 172.18.0.2 with 32 bytes of data:

Reply from 172.18.0.2: bytes=32 time<1ms TTL=126
Reply from 172.18.0.2: bytes=32 time=12ms TTL=126
Reply from 172.18.0.2: bytes=32 time=12ms TTL=126
Reply from 172.18.0.2: bytes=32 time=11ms TTL=126

Ping statistics for 172.18.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 12ms, Average = 8ms
```