Ex. No:07 Date:03/09/2024

Roll No:231901027

# Examining Network Address Translation (NAT) using Cisco Packet Tracer

**Aim:** Examining Network Address Translation (NAT) using Cisco Packet Tracer involves several steps. NAT is commonly used to allow multiple devices on a local network to share a single public IP address for accessing the internet. Here's how you can set up and examine NAT using Cisco Packet Tracer:

#### 1. Setting Up the Network Topology

- Devices Required:
  - 1. One or more PCs (for testing connectivity)
  - 2. One router (to configure NAT)
  - 3. One switch (to connect the PCs and the router)
  - 4. One server (to simulate an external network, like the internet)
- Steps:
  - 1. **Place the Devices:** Drag and drop the required devices onto the workspace.
  - 2. **Connect the Devices:** Use the appropriate cables (copper straight-through for PCs to the switch, copper cross-over for switch to router) to connect the devices.
  - 3. Assign IP Addresses:
    - Assign private IP addresses (e.g., 192.168.1.0/24) to the PCs and the router's internal interface.
    - Assign a public IP address (e.g., 200.0.0.1/30) to the router's external interface.
    - Assign an IP address to the server that simulates an external network (e.g., 200.0.0.2/30).


## 2. Configuring NAT on the Router

- Steps:
  - 1. Access the Router CLI: Click on the router and go to the CLI tab.
  - 2. Enter Global Configuration Mode:

Router> enable
Router# configure terminal

3, Configure Interfaces:

Set up the internal and external interfaces:




#### 1. Configure NAT Overload (PAT):

Define an access list to match the internal IP range:

```
Router(config)# access-list 1 permit 192.168.1.0 0.0.0.255
```

Configure NAT to translate the internal addresses to the external address:



This configures PAT (Port Address Translation), which allows multiple internal IPs to share a single external IP.

## 3. Testing NAT


- Steps:
  - 1. Ping from a PC to the External Network:
    - From one of the PCs, open the command prompt and try to ping the external server (e.g., ping 200.0.0.2).
  - 2. Verify NAT Translations:

On the router CLI, check the NAT translation table to see the active translations:

Router# show ip nat translations

#### **Observe the Output:**

The NAT translation table should show the mapping of the internal private IP addresses to the external public IP.



## 4. Observing the Traffic

• Use the simulation mode in Packet Tracer to visually observe the NAT process as packets move from the internal network to the external network.

## 5. Saving the Configuration

Don't forget to save the configuration on the router to avoid losing the settings:

Router# copy running-config startup-config

By following these steps, you can effectively examine and understand how NAT works in a network environment using Cisco Packet Tracer.

#### Result:

Thus, the experiment of Network Address Translation(NAT) was Examined.