## Création d'un compte Wifi GUEST




Pour connecter une poste dans le VLAN GUEST, il faut connaitre son adresse MAC.


Aller sur le serveur RADIUS à l'adresse suivant : http://176.20.10.100:2002/

Entrer l'identifiant de connexion. Il faut être administrateur du Serveur Radius.

Ensuit sélectionner l'onglet User Setup



Entrer l'adresse Mac sans majuscule et sans séparateur, puis faire find



Si l'adresse n'est pas trouvé, il n'y a aucun compte existant, on peut donc faire add/edit

Copier et Coller l'adresse MAC (en minuscule) dans les 4 champs Password et le Default Group, qui sera Vlan4 GUEST.

Puis on valide avec submit.

	Supplem	entary User Info		
al Name	ncabot			
scription	cabot num	а		
-	Y	ser Setup		
		ser Setup		
Password	Authentication:		CiscoSecure	Database -
Cis	coSecure PAP (Also used for	CHAP/MS-CHAP/AR		
Г				checked.)
- 1	Password	•••	••••	
[	Confirm Password	10.66	•••	
EZ Canada	COTTABACO OTTABADADA			
Separa	te (CHAP/MS-CHAP/ARAP	)		
	Password		••••	
	Password Confirm Password	•••	•••	password for a
When a to	Password Confirm Password Ken server is used for authent user allows CHAP authentic	ication, supplying a sep ation. This is especially	parate CHAP puseful when	
When a to	Password Confirm Password Ken server is used for authent user allows CHAP authentic	ication, supplying a sep ation. This is especially hich the user is assigned	parate CHAP puseful when	
When a to	Password Confirm Password  Ken server is used for authent user allows CHAP authentic  Group to wi	ication, supplying a sep ation. This is especially hich the user is assigned	parate CHAP puseful when	
When a to	Password Confirm Password  Ken server is used for authent user allows CHAP authentic  Group to wi	ication, supplying a sep ation. This is especially hich the user is assigned	parate CHAP puseful when	
When a to token card is enabled	Password Confirm Password  Ken server is used for authent user allows CHAP authentic  Group to wi	ication, supplying a sep ation. This is especially hich the user is assigned	parate CHAP puseful when	
When a to token card is enabled	Password Confirm Password  ken server is used for authent user allows CHAP authentica  Group to wi	ication, supplying a sep ation. This is especially hich the user is assigned	parate CHAP puseful when	
When a to token card is enabled  Us	Password Confirm Password  Ken server is used for authent user allows CHAP authentica  Group to will Vlan4 GUEST	ication, supplying a sep ation. This is especially hich the user is assigned	parate CHAP puseful when	
When a to token card is enabled  Us No	Password Confirm Password Ken server is used for authent user allows CHAP authentica  Group to wi Vian4 GUEST  e group setting callback allowed	ication, supplying a sepation. This is especially hich the user is assigned.  Callback	parate CHAP puseful when	

Ensuit il faut ajouter le réseau wifi sur le poste utilisateur :


Aller dans centre de réseau et partage



Onglet sur la gauche « Gérer les réseaux sans fil »

Puis l'onglet **ajouter** :

« Créer un profil réseau manuellement »



Nom du réseau : SSID\_E&C\_GUEST.

Type de sécurité Open.

Cocher « lancer automatiquement cette connexion » et « Me connecter même si le réseau ne diffuse pas son nom »