

Win32 - Error Codes (0 - 999)



Win32 - Error Codes (2000 - 5999)



Win32 - Error Codes (1000 - 1999)

The following table provides a list of Win32 error codes.

Code	Description	Name
1001	Recursion too deep; the stack overflowed.	ERROR_STACK_OVERFLOW
1002	The window cannot act on the sent message.	ERROR_INVALID_MESSAGE
1003	Cannot complete this function.	ERROR_CAN_NOT_COMPLETE
1004	Invalid flags.	ERROR_INVALID_FLAGS
1005	The volume does not contain a recognized file system. Please make sure that all required file system drivers are loaded and that the volume is not corrupted.	ERROR_UNRECOGNIZED_VOLUME
1006	The volume for a file has been externally altered so that the opened file is no longer valid.	ERROR_FILE_INVALID
1007	The requested operation cannot be performed in full-screen mode.	ERROR_FULLSCREEN_MODE
1008	An attempt was made to reference a token that does not exist.	ERROR_NO_TOKEN
1009	The configuration registry database is corrupt.	ERROR_BADDB
1010	The configuration registry key is invalid.	ERROR_BADKEY
1011	The configuration registry key could not be opened.	ERROR_CANTOPEN
1012	The configuration registry key could not be read.	ERROR_CANTREAD
1013	The configuration registry key could not be written.	ERROR_CANTWRITE
1014	One of the files in the registry database had to be recovered by use of a log or alternate copy. The recovery was successful.	ERROR_REGISTRY_RECOVERED
1015	The registry is corrupted. The structure of one of the files that contains registry data is corrupted, or the system's image of the file in memory is corrupted, or the file could not be recovered because the alternate copy or log was absent or corrupted.	ERROR_REGISTRY_CORRUPT
1016	An I/O operation initiated by the registry failed unrecoverably. The registry could not read in, or write out, or flush, one of the files that contain the system's image of the registry.	ERROR_REGISTRY_IO_FAILED
1017	The system has attempted to load or restore a file into the registry, but the specified file is not in a registry file format.	ERROR_NOT_REGISTRY_FILE
1018	Illegal operation attempted on a registry key that has been marked for deletion.	ERROR_KEY_DELETED
1019	System could not allocate the required space in a registry log.	ERROR_NO_LOG_SPACE
1020	Cannot create a symbolic link in a registry key that already has subkeys or values.	ERROR_KEY_HAS_CHILDREN
1021	Cannot create a stable subkey under a volatile parent key.	ERROR_CHILD_MUST_BE_VOLATILE
1022	A notify change request is being completed and the information is not being returned in the caller's buffer. The caller now must enumerate the files to find the changes.	ERROR_NOTIFY_ENUM_DIR

10/2//24,	12.23 1 W	132 - Endi Godes (1000 - 1999)
	A stop control has been sent to a service that other running services are dependent on.	ERROR_DEPENDENT_SERVICES_RUNNING
1052	The requested control is not valid for this service.	ERROR_INVALID_SERVICE_CONTROL
	The service did not respond to the start or control request in a timely fashion.	ERROR_SERVICE_REQUEST_TIMEOUT
1054	A thread could not be created for the service.	ERROR_SERVICE_NO_THREAD
1055	The service database is locked.	ERROR_SERVICE_DATABASE_LOCKED
1056	An instance of the service is already running.	ERROR SERVICE ALREADY RUNNING
1057	The account name is invalid or does not exist.	ERROR_INVALID_SERVICE_ACCOUNT
	The service cannot be started, either because it is disabled or because it has no enabled devices associated with it.	ERROR_SERVICE_DISABLED
1059	Circular service dependency was specified.	ERROR_CIRCULAR_DEPENDENCY
	The specified service does not exist as an installed service.	ERROR_SERVICE_DOES_NOT_EXIST
	The service cannot accept control messages at this time.	ERROR_SERVICE_CANNOT_ACCEPT_CTRL
1062	The service has not been started.	ERROR_SERVICE_NOT_ACTIVE
	The service process could not connect to the service controller.	ERROR_FAILED_SERVICE_CONTROLLER_CONNECT
	An exception occurred in the service when handling the control request.	ERROR_EXCEPTION_IN_SERVICE
1065	The database specified does not exist.	ERROR_DATABASE_DOES_NOT_EXIST
	The service has returned a service-specific error code.	ERROR_SERVICE_SPECIFIC_ERROR
1067	The process terminated unexpectedly.	ERROR_PROCESS_ABORTED
1068	The dependency service or group failed to start.	ERROR_SERVICE_DEPENDENCY_FAIL
1069	The service did not start due to a logon failure.	ERROR_SERVICE_LOGON_FAILED
	After starting, the service hung in a start-pending state.	ERROR_SERVICE_START_HANG
1071	The specified service database lock is invalid.	ERROR_INVALID_SERVICE_LOCK
1072	The specified service has been marked for deletion.	ERROR_SERVICE_MARKED_FOR_DELETE
1073	The specified service already exists.	ERROR_SERVICE_EXISTS
	The system is currently running with the last-knowngood configuration.	ERROR_ALREADY_RUNNING_LKG
	The dependency service does not exist or has been marked for deletion.	ERROR_SERVICE_DEPENDENCY_DELETED
	The current boot has already been accepted for use as the last-known-good control set.	ERROR_BOOT_ALREADY_ACCEPTED
	No attempts to start the service have been made since the last boot.	ERROR_SERVICE_NEVER_STARTED
	The name is already in use as either a service name or a service display name.	ERROR_DUPLICATE_SERVICE_NAME
	The account specified for this service is different from the account specified for other services running in the same process.	ERROR_DIFFERENT_SERVICE_ACCOUNT
	Failure actions can only be set for Win32 services, not for drivers.	ERROR_CANNOT_DETECT_DRIVER_FAILURE
	This service runs in the same process as the service control manager. Therefore, the service control manager cannot take action if this service's process terminates unexpectedly.	ERROR_CANNOT_DETECT_PROCESS_ABORT
	No recovery program has been configured for this service.	ERROR_NO_RECOVERY_PROGRAM
	The executable program that this service is configured to run in does not implement the service.	ERROR_SERVICE_NOT_IN_EXE
1100	The physical end of the tape has been reached.	ERROR_END_OF_MEDIA
1101	A tape access reached a filemark.	ERROR_FILEMARK_DETECTED

1103 1104 1105 1106	The beginning of the tape or a partition was encountered. A tape access reached the end of a set of files. No more data is on the tape. Tape could not be partitioned. When accessing a new tape of a multivolume partition, the current block size is incorrect. Tape partition information could not be found when loading a tape.	ERROR_BEGINNING_OF_MEDIA ERROR_SETMARK_DETECTED ERROR_NO_DATA_DETECTED ERROR_PARTITION_FAILURE ERROR_INVALID_BLOCK_LENGTH
1104 1105 1106	No more data is on the tape. Tape could not be partitioned. When accessing a new tape of a multivolume partition, the current block size is incorrect. Tape partition information could not be found when	ERROR_NO_DATA_DETECTED ERROR_PARTITION_FAILURE
1105 1106	Tape could not be partitioned. When accessing a new tape of a multivolume partition, the current block size is incorrect. Tape partition information could not be found when	ERROR_PARTITION_FAILURE
1106	When accessing a new tape of a multivolume partition, the current block size is incorrect. Tape partition information could not be found when	
	partition, the current block size is incorrect. Tape partition information could not be found when	ERROR_INVALID_BLOCK_LENGTH
ļ		
	loading a tape.	ERROR_DEVICE_NOT_PARTITIONED
1108	Unable to lock the media eject mechanism.	ERROR_UNABLE_TO_LOCK_MEDIA
1109	Unable to unload the media.	ERROR_UNABLE_TO_UNLOAD_MEDIA
1110	The media in the drive can have changed.	ERROR_MEDIA_CHANGED
1111	The I/O bus was reset.	ERROR_BUS_RESET
1112	No media in drive.	ERROR_NO_MEDIA_IN_DRIVE
	No mapping for the Unicode character exists in the target multi-byte code page.	ERROR_NO_UNICODE_TRANSLATION
	A dynamic link library (DLL) initialization routine failed.	ERROR_DLL_INIT_FAILED
1115	A system shutdown is in progress.	ERROR_SHUTDOWN_IN_PROGRESS
	Unable to abort the system shutdown because no shutdown was in progress.	ERROR_NO_SHUTDOWN_IN_PROGRESS
	The request could not be performed because of an I/O device error.	ERROR_IO_DEVICE
	No serial device was successfully initialized. The serial driver will unload.	ERROR_SERIAL_NO_DEVICE
į	Unable to open a device that was sharing an interrupt request (IRQ) with other devices. At least one other device that uses that IRQ was already opened.	ERROR_IRQ_BUSY
,	A serial I/O operation was completed by another write to the serial port. (The IOCTL_SERIAL_XOFF_COUNTER reached zero.)	ERROR_MORE_WRITES
1121	A serial I/O operation completed because the timeout period expired. (The IOCTL_SERIAL_XOFF_COUNTER did not reach zero.)	ERROR_COUNTER_TIMEOUT
1122	No ID address mark was found on the floppy disk.	ERROR_FLOPPY_ID_MARK_NOT_FOUND
	Mismatch between the floppy disk sector ID field and the floppy disk controller track address.	ERROR_FLOPPY_WRONG_CYLINDER
1124	The floppy disk controller reported an error that is not recognized by the floppy disk driver.	ERROR_FLOPPY_UNKNOWN_ERROR
	The floppy disk controller returned inconsistent results in its registers.	ERROR_FLOPPY_BAD_REGISTERS
	While accessing the hard disk, a recalibrate operation failed, even after retries.	ERROR_DISK_RECALIBRATE_FAILED
	While accessing the hard disk, a disk operation failed even after retries.	ERROR_DISK_OPERATION_FAILED
	While accessing the hard disk, a disk controller reset was needed, but even that failed.	ERROR_DISK_RESET_FAILED
1129	Physical end of tape encountered.	ERROR_EOM_OVERFLOW
	Not enough server storage is available to process this command.	ERROR_NOT_ENOUGH_SERVER_MEMORY
1131	A potential deadlock condition has been detected.	ERROR_POSSIBLE_DEADLOCK
	The base address or the file offset specified does not have the proper alignment.	ERROR_MAPPED_ALIGNMENT
	An attempt to change the system power state was vetoed by another application or driver.	ERROR_SET_POWER_STATE_VETOED

10/27/24,	12:23 PM W	in32 - Error Codes (1000 - 1999)
1141	The system BIOS failed an attempt to change the system power state.	ERROR_SET_POWER_STATE_FAILED
1142	An attempt was made to create more links on a file than the file system supports.	ERROR_TOO_MANY_LINKS
1150	The specified program requires a newer version of Windows.	ERROR_OLD_WIN_VERSION
1151	The specified program is not a Windows or MS-DOS program.	ERROR_APP_WRONG_OS
1152	Cannot start more than one instance of the specified program.	ERROR_SINGLE_INSTANCE_APP
1153	The specified program was written for an earlier version of Windows.	ERROR_RMODE_APP
1154	One of the library files needed to run this application is damaged.	ERROR_INVALID_DLL
1155	No application is associated with the specified file fo this operation.	ERROR_NO_ASSOCIATION
1156	An error occurred in sending the command to the application.	ERROR_DDE_FAIL
1157	One of the library files needed to run this application cannot be found.	ERROR_DLL_NOT_FOUND
1158	The current process has used all of its system allowance of handles for Window Manager objects.	ERROR_NO_MORE_USER_HANDLES
1159	The message can be used only with synchronous operations.	ERROR_MESSAGE_SYNC_ONLY
1160	The indicated source element has no media.	ERROR_SOURCE_ELEMENT_EMPTY
1161	The indicated destination element already contains media.	ERROR_DESTINATION_ELEMENT_FULL
1162	The indicated element does not exist.	ERROR_ILLEGAL_ELEMENT_ADDRESS
1163	The indicated element is part of a magazine that is not present.	ERROR_MAGAZINE_NOT_PRESENT
1164	The indicated device requires reinitialization due to hardware errors.	ERROR_DEVICE_REINITIALIZATION_NEEDED
1165	The device has indicated that cleaning is required before further operations are attempted.	ERROR_DEVICE_REQUIRES_CLEANING
1166	The device has indicated that its door is open.	ERROR_DEVICE_DOOR_OPEN
1167	The device is not connected.	ERROR_DEVICE_NOT_CONNECTED
1168	Element not found.	ERROR_NOT_FOUND
1169	There was no match for the specified key in the index.	ERROR_NO_MATCH
1170	The property set specified does not exist on the object.	ERROR_SET_NOT_FOUND
1171	The point passed to ${\sf GetMouseMovePointsEx}$ is not in the buffer.	ERROR_POINT_NOT_FOUND
1172	The tracking (workstation) service is not running.	ERROR_NO_TRACKING_SERVICE
1173	The Volume ID could not be found.	ERROR_NO_VOLUME_ID
1174	The specified Very Large Memory (64-bit) operation is invalid.	ERROR_INVALID_VLM_OPERATION
1175	Unable to remove the file to be replaced.	ERROR_UNABLE_TO_REMOVE_REPLACED
1176	Unable to move the replacement file to the file to be replaced. The file to be replaced has retained its original name.	ERROR_UNABLE_TO_MOVE_REPLACEMENT
1177	Unable to move the replacement file to the file to be replaced. The file to be replaced has been renamed using the backup name.	ERROR_UNABLE_TO_MOVE_REPLACEMENT_2
1178	The volume change journal is being deleted.	ERROR_JOURNAL_DELETE_IN_PROGRESS
1179	The volume change journal service is not active.	ERROR_JOURNAL_NOT_ACTIVE
1180	A file was found, but it cannot be the correct file.	ERROR_POTENTIAL_FILE_FOUND
1181	The journal entry has been deleted from the journal.	ERROR_JOURNAL_ENTRY_DELETED

		,
1200	The specified device name is invalid.	ERROR_BAD_DEVICE
1201	The device is not currently connected but it is a remembered connection.	ERROR_CONNECTION_UNAVAIL
1202	An attempt was made to remember a device that had previously been remembered.	ERROR_DEVICE_ALREADY_REMEMBERED
1203	No network provider accepted the given network path.	ERROR_NO_NET_OR_BAD_PATH
1204	The specified network provider name is invalid.	ERROR_BAD_PROVIDER
1205	Unable to open the network connection profile.	ERROR_CANNOT_OPEN_PROFILE
1206	The network connection profile is corrupted.	ERROR_BAD_PROFILE
1207	Cannot enumerate a noncontainer.	ERROR_NOT_CONTAINER
1208	An extended error has occurred.	ERROR_EXTENDED_ERROR
1209	The format of the specified group name is invalid.	ERROR_INVALID_GROUPNAME
1210	The format of the specified computer name is invalid.	ERROR_INVALID_COMPUTERNAME
1211	The format of the specified event name is invalid.	ERROR_INVALID_EVENTNAME
1212	The format of the specified domain name is invalid.	ERROR_INVALID_DOMAINNAME
1213	The format of the specified service name is invalid.	ERROR INVALID SERVICENAME
1214	The format of the specified network name is invalid.	ERROR INVALID NETNAME
1215	The format of the specified share name is invalid.	ERROR INVALID SHARENAME
1216	The format of the specified password is invalid.	ERROR INVALID PASSWORDNAME
1217	The format of the specified message name is invalid.	
1218	The format of the specified message destination is invalid.	ERROR_INVALID_MESSAGEDEST
1219	The credentials supplied conflict with an existing set of credentials.	ERROR_SESSION_CREDENTIAL_CONFLICT
1220	An attempt was made to establish a session to a network server, but there are already too many sessions established to that server.	ERROR_REMOTE_SESSION_LIMIT_EXCEEDED
1221	The workgroup or domain name is already in use by another computer on the network.	ERROR_DUP_DOMAINNAME
1222	The network is not present or not started.	ERROR_NO_NETWORK
1223	The operation was canceled by the user.	ERROR_CANCELED
1224	The requested operation cannot be performed on a file with a user-mapped section open.	ERROR_USER_MAPPED_FILE
1225	The remote system refused the network connection.	ERROR_CONNECTION_REFUSED
1226	The network connection was gracefully closed.	ERROR_GRACEFUL_DISCONNECT
1227	The network transport endpoint already has an address associated with it.	ERROR_ADDRESS_ALREADY_ASSOCIATED
1228	An address has not yet been associated with the network endpoint.	ERROR_ADDRESS_NOT_ASSOCIATED
1229	An operation was attempted on a nonexistent network connection.	ERROR_CONNECTION_INVALID
1230	An invalid operation was attempted on an active network connection.	ERROR_CONNECTION_ACTIVE
1231	The remote network is not reachable by the transport.	ERROR_NETWORK_UNREACHABLE
1232	The remote system is not reachable by the transport.	ERROR_HOST_UNREACHABLE
1233	The remote system does not support the transport protocol.	ERROR_PROTOCOL_UNREACHABLE
1234	No service is operating at the destination network endpoint on the remote system.	ERROR_PORT_UNREACHABLE
1235	The request was aborted.	ERROR_REQUEST_ABORTED
1236	The network connection was aborted by the local system.	ERROR_CONNECTION_ABORTED
1237	The operation could not be completed. A retry should be performed.	ERROR_RETRY

1238	A connection to the server could not be made because the limit on the number of concurrent connections for this account has been reached.	ERROR_CONNECTION_COUNT_LIMIT
1239	Attempting to log in during an unauthorized time of day for this account.	ERROR_LOGIN_TIME_RESTRICTION
1240	The account is not authorized to log in from this station.	ERROR_LOGIN_WKSTA_RESTRICTION
1241	The network address could not be used for the operation requested.	ERROR_INCORRECT_ADDRESS
1242	The service is already registered.	ERROR_ALREADY_REGISTERED
1243	The specified service does not exist.	ERROR_SERVICE_NOT_FOUND
1244	The operation being requested was not performed because the user has not been authenticated.	ERROR_NOT_AUTHENTICATED
1245	The operation being requested was not performed because the user has not logged on to the network. The specified service does not exist.	ERROR_NOT_LOGGED_ON
1246	Continue with work in progress.	ERROR_CONTINUE
1247	An attempt was made to perform an initialization operation when initialization has already been completed.	ERROR_ALREADY_INITIALIZED
1248	No more local devices.	ERROR_NO_MORE_DEVICES
1249	The specified site does not exist.	ERROR_NO_SUCH_SITE
1250	A domain controller with the specified name already exists.	ERROR_DOMAIN_CONTROLLER_EXISTS
1251	This operation is supported only when you are connected to the server.	ERROR_ONLY_IF_CONNECTED
1300	Not all privileges referenced are assigned to the caller.	ERROR_NOT_ALL_ASSIGNED
1301	Some mapping between account names and security IDs was not done.	ERROR_SOME_NOT_MAPPED
1302	No system quota limits are specifically set for this account.	ERROR_NO_QUOTAS_FOR_ACCOUNT
1303	No encryption key is available. A well-known encryption key was returned.	ERROR_LOCAL_USER_SESSION_KEY
1304	The Windows NT password is too complex to be converted to a LAN Manager password. The LAN Manager password returned is a NULL string.	ERROR_NULL_LM_PASSWORD
1305	The revision level is unknown.	ERROR_UNKNOWN_REVISION
1306	Indicates two revision levels are incompatible.	ERROR_REVISION_MISMATCH
1307	This security ID cannot be assigned as the owner of this object.	ERROR_INVALID_OWNER
1308	This security ID cannot be assigned as the primary group of an object.	ERROR_INVALID_PRIMARY_GROUP
1309	An attempt has been made to operate on an impersonation token by a thread that is not currently impersonating a client.	ERROR_NO_IMPERSONATION_TOKEN
1310	The group cannot be disabled.	ERROR_CANT_DISABLE_MANDATORY
1311	There are currently no logon servers available to service the logon request.	ERROR_NO_LOGON_SERVERS
1312	A specified logon session does not exist. It can already have been terminated.	ERROR_NO_SUCH_LOGON_SESSION
1313	A specified privilege does not exist.	ERROR_NO_SUCH_PRIVILEGE
1314	A required privilege is not held by the client.	ERROR_PRIVILEGE_NOT_HELD
1315	The name provided is not a properly formed account name.	ERROR_INVALID_ACCOUNT_NAME
1316	The specified user already exists.	ERROR_USER_EXISTS
1317	The specified user does not exist.	ERROR_NO_SUCH_USER
1318	The specified group already exists.	ERROR_GROUP_EXISTS

10/27/24,	12:23 PM W	n32 - Error Codes (1000 - 1999)
1319	The specified group does not exist.	ERROR_NO_SUCH_GROUP
1320	Either the specified user account is already a member of the specified group, or the specified group cannot be deleted because it contains a member.	ERROR_MEMBER_IN_GROUP
1321	The specified user account is not a member of the specified group account.	ERROR_MEMBER_NOT_IN_GROUP
1322	The last remaining administration account cannot be disabled or deleted.	ERROR_LAST_ADMIN
1323	Unable to update the password. The value provided as the current password is incorrect.	ERROR_WRONG_PASSWORD
1324	Unable to update the password. The value provided for the new password contains values that are not allowed in passwords.	ERROR_ILL_FORMED_PASSWORD
1325	Unable to update the password because a password update rule has been violated.	ERROR_PASSWORD_RESTRICTION
1326	Logon failure: unknown user name or bad password.	ERROR_LOGON_FAILURE
1327	Logon failure: user account restriction.	ERROR_ACCOUNT_RESTRICTION
1328	Logon failure: account logon time restriction violation.	ERROR_INVALID_LOGON_HOURS
1329	Logon failure: user not allowed to log on to this computer.	ERROR_INVALID_WORKSTATION
1330	Logon failure: the specified account password has expired.	ERROR_PASSWORD_EXPIRED
1331	Logon failure: account currently disabled.	ERROR_ACCOUNT_DISABLED
1332	No mapping between account names and security IDs was done.	ERROR_NONE_MAPPED
1333	Too many local user identifiers (LUIDs) were requested at one time.	ERROR_TOO_MANY_LUIDS_REQUESTED
1334	No more local user identifiers (LUIDs) are available.	ERROR_LUIDS_EXHAUSTED
1335	The subauthority part of a security ID is invalid for this particular use.	ERROR_INVALID_SUB_AUTHORITY
1336	The access control list (ACL) structure is invalid.	ERROR_INVALID_ACL
1337	The security ID structure is invalid.	ERROR_INVALID_SID
1338	The security descriptor structure is invalid.	ERROR_INVALID_SECURITY_DESCR
1340	The inherited access control list (ACL) or access control entry (ACE) could not be built.	ERROR_BAD_INHERITANCE_ACL
1341	The server is currently disabled.	ERROR_SERVER_DISABLED
1342	The server is currently enabled.	ERROR_SERVER_NOT_DISABLED
1343	The value provided was an invalid value for an identifier authority.	ERROR_INVALID_ID_AUTHORITY
1344	No more memory is available for security information updates.	ERROR_ALLOTTED_SPACE_EXCEEDED
1345	The specified attributes are invalid, or incompatible with the attributes for the group as a whole.	ERROR_INVALID_GROUP_ATTRIBUTES
1346	Either a required impersonation level was not provided, or the provided impersonation level is invalid.	ERROR_BAD_IMPERSONATION_LEVEL
1347	Cannot open an anonymous level security token.	ERROR_CANT_OPEN_ANONYMOUS
1348	The validation information class requested was invalid.	ERROR_BAD_VALIDATION_CLASS
1349	The type of the token is inappropriate for its attempted use.	ERROR_BAD_TOKEN_TYPE
1350	Unable to perform a security operation on an object that has no associated security.	
1351	Configuration information could not be read from the domain controller, either because the machine is unavailable, or access has been denied.	ERROR_CANT_ACCESS_DOMAIN_INFO

,	1	
1352	The security account manager (SAM) or local security authority (LSA) server was in the wrong state to perform the security operation.	ERROR_INVALID_SERVER_STATE
1353	The domain was in the wrong state to perform the security operation.	ERROR_INVALID_DOMAIN_STATE
1354	This operation is only allowed for the Primary Domain Controller of the domain.	ERROR_INVALID_DOMAIN_ROLE
1355	The specified domain did not exist.	ERROR_NO_SUCH_DOMAIN
1356	The specified domain already exists.	ERROR DOMAIN EXISTS
1357	An attempt was made to exceed the limit on the number of domains per server.	ERROR_DOMAIN_LIMIT_EXCEEDED
1358	Unable to complete the requested operation because of either a catastrophic media failure or a data structure corruption on the disk.	ERROR_INTERNAL_DB_CORRUPTION
1359	The security account database contains an internal inconsistency.	ERROR_INTERNAL_ERROR
1360	Generic access types were contained in an access mask which should already be mapped to nongeneric types.	ERROR_GENERIC_NOT_MAPPED
1361	A security descriptor is not in the right format (absolute or self-relative).	ERROR_BAD_DESCRIPTOR_FORMAT
1362	The requested action is restricted for use by logon processes only. The calling process has not registered as a logon process.	ERROR_NOT_LOGON_PROCESS
1363	Cannot start a new logon session with an ID that is already in use.	ERROR_LOGON_SESSION_EXISTS
1364	A specified authentication package is unknown.	ERROR_NO_SUCH_PACKAGE
1365	The logon session is not in a state that is consistent with the requested operation.	ERROR_BAD_LOGON_SESSION_STATE
1366	The logon session ID is already in use.	ERROR_LOGON_SESSION_COLLISION
1367	A logon request contained an invalid logon type value.	ERROR_INVALID_LOGON_TYPE
1368	Unable to impersonate using a named pipe until data has been read from that pipe.	ERROR_CANNOT_IMPERSONATE
1369	The transaction state of a registry subtree is incompatible with the requested operation.	ERROR_RXACT_INVALID_STATE
1370	An internal security database corruption has been encountered.	ERROR_RXACT_COMMIT_FAILURE
1371	Cannot perform this operation on built-in accounts.	ERROR_SPECIAL_ACCOUNT
1372	Cannot perform this operation on this built-in special group.	ERROR_SPECIAL_GROUP
1373	Cannot perform this operation on this built-in special user.	ERROR_SPECIAL_USER
1374	The user cannot be removed from a group because the group is currently the user's primary group.	ERROR_MEMBERS_PRIMARY_GROUP
1375	The token is already in use as a primary token.	ERROR_TOKEN_ALREADY_IN_USE
1376	The specified local group does not exist.	ERROR_NO_SUCH_ALIAS
1377	The specified account name is not a member of the local group.	ERROR_MEMBER_NOT_IN_ALIAS
1378	The specified account name is already a member of the local group.	ERROR_MEMBER_IN_ALIAS
1379	The specified local group already exists.	ERROR_ALIAS_EXISTS
1380	Logon failure: the user has not been granted the requested logon type at this computer.	ERROR_LOGON_NOT_GRANTED
1381	The maximum number of secrets that can be stored in a single system has been exceeded.	ERROR_TOO_MANY_SECRETS
1382	The length of a secret exceeds the maximum length allowed.	ERROR_SECRET_TOO_LONG

10/21/24,	12.23 I WI	132 - Ellor Godes (1000 - 1999)
1383	The local security authority database contains an internal inconsistency.	ERROR_INTERNAL_DB_ERROR
1384	During a logon attempt, the user's security context accumulated too many security IDs.	ERROR_TOO_MANY_CONTEXT_IDS
1385	Logon failure: the user has not been granted the requested logon type at this computer.	ERROR_LOGON_TYPE_NOT_GRANTED
1386	A cross-encrypted password is necessary to change a user password.	ERROR_NT_CROSS_ENCRYPTION_REQUIRED
1387	A new member could not be added to a local group because the member does not exist.	ERROR_NO_SUCH_MEMBER
1388	A new member could not be added to a local group because the member has the wrong account type.	ERROR_INVALID_MEMBER
1389	Too many security IDs have been specified.	ERROR_TOO_MANY_SIDS
1390	A cross-encrypted password is necessary to change this user password.	ERROR_LM_CROSS_ENCRYPTION_REQUIRED
1391	Indicates an ACL contains no inheritable components.	ERROR_NO_INHERITANCE
1392	The file or directory is corrupted and unreadable.	ERROR_FILE_CORRUPT
1393	The disk structure is corrupted and unreadable.	ERROR_DISK_CORRUPT
1394	There is no user session key for the specified logon session.	ERROR_NO_USER_SESSION_KEY
1395	The service being accessed is licensed for a particular number of connections. No more connections can be made to the service at this time because there are already as many connections as the service can accept.	ERROR_LICENSE_QUOTA_EXCEEDED
1396	Logon Failure: The target account name is incorrect.	ERROR_WRONG_TARGET_NAME
1397	Mutual Authentication failed. The server's password is out of date at the domain controller.	ERROR_MUTUAL_AUTH_FAILED
1398	There is a time difference between the client and server.	ERROR_TIME_SKEW
1400	Invalid window handle.	ERROR_INVALID_WINDOW_HANDLE
1401	Invalid menu handle.	ERROR_INVALID_MENU_HANDLE
1402	Invalid cursor handle.	ERROR_INVALID_CURSOR_HANDLE
1403	Invalid accelerator table handle.	ERROR_INVALID_ACCEL_HANDLE
1404	Invalid hook handle.	ERROR_INVALID_HOOK_HANDLE
1405	Invalid handle to a multiple-window position structure.	ERROR_INVALID_DWP_HANDLE
1406	Cannot create a top-level child window.	ERROR_TLW_WITH_WSCHILD
1407	Cannot find window class.	ERROR_CANNOT_FIND_WND_CLASS
1408	Invalid window; it belongs to other thread.	ERROR_WINDOW_OF_OTHER_THREAD
1409	Hot key is already registered.	ERROR_HOTKEY_ALREADY_REGISTERED
1410	Class already exists.	ERROR_CLASS_ALREADY_EXISTS
1411	Class does not exist.	ERROR_CLASS_DOES_NOT_EXIST
1412	Class still has open windows.	ERROR_CLASS_HAS_WINDOWS
1413	Invalid index.	ERROR_INVALID_INDEX
1414	Invalid icon handle.	ERROR_INVALID_ICON_HANDLE
1415	Using private DIALOG window words.	ERROR_PRIVATE_DIALOG_INDEX
1416	The list box identifier was not found.	ERROR_LISTBOX_ID_NOT_FOUND
1417	No wildcards were found.	ERROR_NO_WILDCARD_CHARACTERS
1418	Thread does not have a clipboard open.	ERROR_CLIPBOARD_NOT_OPEN
1419	Hot key is not registered.	ERROR_HOTKEY_NOT_REGISTERED
1420	The window is not a valid dialog window.	ERROR_WINDOW_NOT_DIALOG
1421	Control ID not found.	ERROR_CONTROL_ID_NOT_FOUND
1422	Invalid message for a combo box because it does not have an edit control.	ERROR_INVALID_COMBOBOX_MESSAGE

		•
1423	The window is not a combo box.	ERROR_WINDOW_NOT_COMBOBOX
1424	Height must be less than 256.	ERROR_INVALID_EDIT_HEIGHT
1425	Invalid device context (DC) handle.	ERROR_DC_NOT_FOUND
1426	Invalid hook procedure type.	ERROR_INVALID_HOOK_FILTER
1427	Invalid hook procedure.	ERROR_INVALID_FILTER_PROC
1428	Cannot set nonlocal hook without a module handle.	ERROR_HOOK_NEEDS_HMOD
1429	This hook procedure can only be set globally.	ERROR_GLOBAL_ONLY_HOOK
1430	The journal hook procedure is already installed.	ERROR_JOURNAL_HOOK_SET
1431	The hook procedure is not installed.	ERROR_HOOK_NOT_INSTALLED
1432	Invalid message for single-selection list box.	ERROR_INVALID_LB_MESSAGE
1433	LB_SETCOUNT sent to non-lazy list box.	ERROR_SETCOUNT_ON_BAD_LB
1434	This list box does not support tab stops.	ERROR_LB_WITHOUT_TABSTOPS
1435	Cannot destroy object created by another thread.	ERROR_DESTROY_OBJECT_OF_OTHER_THREAD
1436	Child windows cannot have menus.	ERROR_CHILD_WINDOW_MENU
1437	The window does not have a system menu.	ERROR_NO_SYSTEM_MENU
1438	Invalid message box style.	ERROR_INVALID_MSGBOX_STYLE
1439	Invalid system-wide (SPI_*) parameter.	ERROR_INVALID_SPI_VALUE
1440	Screen already locked.	ERROR_SCREEN_ALREADY_LOCKED
1441	All handles to windows in a multiple-window position structure must have the same parent.	ERROR_HWNDS_HAVE_DIFF_PARENT
1442	The window is not a child window.	ERROR_NOT_CHILD_WINDOW
1443	Invalid GW_* command.	ERROR_INVALID_GW_COMMAND
1444	Invalid thread identifier.	ERROR_INVALID_THREAD_ID
1445	Cannot process a message from a window that is not a multiple document interface (MDI) window.	ERROR_NON_MDICHILD_WINDOW
1446	Context menu already active.	ERROR_POPUP_ALREADY_ACTIVE
1447	The window does not have scroll bars.	ERROR_NO_SCROLLBARS
1448	Scroll bar range cannot be greater than 0x7FFF.	ERROR_INVALID_SCROLLBAR_RANGE
1449	Cannot show or remove the window in the way specified.	ERROR_INVALID_SHOWWIN_COMMAND
1450	Insufficient system resources exist to complete the requested service.	ERROR_NO_SYSTEM_RESOURCES
1451	Insufficient system resources exist to complete the requested service.	ERROR_NONPAGED_SYSTEM_RESOURCES
1452	Insufficient system resources exist to complete the requested service.	ERROR_PAGED_SYSTEM_RESOURCES
1453	Insufficient quota to complete the requested service.	ERROR_WORKING_SET_QUOTA
1454	Insufficient quota to complete the requested service.	ERROR_PAGEFILE_QUOTA
1455	The paging file is too small for this operation to complete.	ERROR_COMMITMENT_LIMIT
1456	A menu item was not found.	ERROR_MENU_ITEM_NOT_FOUND
1457	Invalid keyboard layout handle.	ERROR INVALID KEYBOARD HANDLE
1458	Hook type not allowed.	ERROR_HOOK_TYPE_NOT_ALLOWED
1459	This operation requires an interactive window station.	ERROR_REQUIRES_INTERACTIVE_WINDOWSTATION
1460	This operation returned because the timeout period expired.	ERROR_TIMEOUT
1461	Invalid monitor handle.	ERROR_INVALID_MONITOR_HANDLE
1500	The event log file is corrupted.	ERROR_EVENTLOG_FILE_CORRUPT
1501	No event log file could be opened, so the event logging service did not start.	ERROR_EVENTLOG_CANT_START
1502		ERROR_LOG_FILE_FULL
1503	The event log file has changed between read operations.	ERROR_EVENTLOG_FILE_CHANGED
1601	Failure accessing installation service.	ERROR_INSTALL_SERVICE_FAILURE

10/27/24,	12:23 PM W	in32 - Error Codes (1000 - 1999)
1602	User canceled installation.	ERROR_INSTALL_USEREXIT
1603	Fatal error during installation.	ERROR_INSTALL_FAILURE
1604	Installation suspended, incomplete.	ERROR_INSTALL_SUSPEND
1605	Product is not installed.	ERROR_UNKNOWN_PRODUCT
1606	Feature ID not registered.	ERROR_UNKNOWN_FEATURE
1607	Component ID not registered.	ERROR_UNKNOWN_COMPONENT
1608	Unknown property.	ERROR_UNKNOWN_PROPERTY
1609	Handle is in an invalid state.	ERROR_INVALID_HANDLE_STATE
1610	Configuration data corrupt.	ERROR_BAD_CONFIGURATION
1611	Component qualifier not present.	ERROR_INDEX_ABSENT
1612	Install source unavailable.	ERROR_INSTALL_SOURCE_ABSENT
1613	Database version unsupported.	ERROR_INSTALL_PACKAGE_VERSION
1614	Product is uninstalled.	ERROR_PRODUCT_UNINSTALLED
1615	SQL query syntax invalid or unsupported.	ERROR_BAD_QUERY_SYNTAX
1616	Record field does not exist.	ERROR_INVALID_FIELD
1617	The device has been removed.	ERROR_DEVICE_REMOVED
1618	An installation is in progress.	ERROR_INSTALL_ALREADY_RUNNING
1619	Installation package could not be opened.	ERROR_INSTALL_PACKAGE_OPEN_FAILED
1620	Installation package invalid.	ERROR_INSTALL_PACKAGE_INVALID
1621	Could not initialize installer UserInterface.	ERROR_INSTALL_UI_FAILURE
1622	Error opening installation log file.	ERROR_INSTALL_LOG_FAILURE
1623	Product language not supported by system.	ERROR_INSTALL_LANGUAGE_UNSUPPORTED
1624	Error applying transform to install package.	ERROR_INSTALL_TRANSFORM_FAILURE
1625	Install package signature not accepted.	ERROR_INSTALL_PACKAGE_REJECTED
1626	Function could not be executed.	ERROR_FUNCTION_NOT_CALLED
1627	Function failed during execution.	ERROR_FUNCTION_FAILED
1628	Invalid or unknown table specified.	ERROR_INVALID_TABLE
1629	Data supplied is of wrong type.	ERROR_DATATYPE_MISMATCH
1630	Data of this type is not supported.	ERROR_UNSUPPORTED_TYPE
1631	Unable to create requested object.	ERROR_CREATE_FAILED
1632	Temp folder is full or inaccessible.	ERROR_INSTALL_TEMP_UNWRITABLE
1633	Product platform not supported.	ERROR_INSTALL_PLATFORM_UNSUPPORTED
1634	Component not used on this computer.	ERROR_INSTALL_NOTUSED
1635	Patch package could not be opened.	ERROR_PATCH_PACKAGE_OPEN_FAILED
1636	Patch package invalid.	ERROR_PATCH_PACKAGE_INVALID
1637	Patch package unsupported.	ERROR_PATCH_PACKAGE_UNSUPPORTED.
1638	Invalid command line argument.	ERROR_INVALID_COMMAND_LINE
1700	The string binding is invalid.	RPC_S_INVALID_STRING_BINDING
1701	The binding handle is not the correct type.	RPC_S_WRONG_KIND_OF_BINDING
1702	The binding handle is invalid.	RPC_S_INVALID_BINDING
1703	The RPC protocol sequence is not supported.	RPC_S_PROTSEQ_NOT_SUPPORTED
1704	The RPC protocol sequence is invalid.	RPC_S_INVALID_RPC_PROTSEQ
1705	The string universal unique identifier (UUID) is invalid.	RPC_S_INVALID_STRING_UUID
1706	The endpoint format is invalid.	RPC_S_INVALID_ENDPOINT_FORMAT
1707	The network address is invalid.	RPC_S_INVALID_NET_ADDR
1708	No endpoint was found.	RPC_S_NO_ENDPOINT_FOUND
1709	The timeout value is invalid.	RPC_S_INVALID_TIMEOUT
1710	The object universal unique identifier (UUID) was no found.	t RPC_S_OBJECT_NOT_FOUND
1711	The object universal unique identifier (UUID) has already been registered.	RPC_S_ALREADY_REGISTERED

10/27/24,	12:23 PM Wi	n32 - Error Codes (1000 - 1999)
1712	The type universal unique identifier (UUID) has already been registered.	RPC_S_TYPE_ALREADY_REGISTERED
1713	The RPC server is already listening.	RPC_S_ALREADY_LISTENING
1714	No protocol sequences have been registered.	RPC_S_NO_PROTSEQS_REGISTERED
1715	The RPC server is not listening.	RPC_S_NOT_LISTENING
1716	The manager type is unknown.	RPC_S_UNKNOWN_MGR_TYPE
1717	The interface is unknown.	RPC_S_UNKNOWN_IF
1718	There are no bindings.	RPC_S_NO_BINDINGS
1719	There are no protocol sequences.	RPC_S_NO_PROTSEQS
1720	The endpoint cannot be created.	RPC_S_CANT_CREATE_ENDPOINT
1721	Not enough resources are available to complete this operation.	RPC_S_OUT_OF_RESOURCES
1722	The RPC server is unavailable.	RPC_S_SERVER_UNAVAILABLE
1723	The RPC server is too busy to complete this operation.	RPC_S_SERVER_TOO_BUSY
1724	The network options are invalid.	RPC_S_INVALID_NETWORK_OPTIONS
1725	There are no remote procedure calls active on this thread.	RPC_S_NO_CALL_ACTIVE
1726	The remote procedure call failed.	RPC_S_CALL_FAILED
1727	The remote procedure call failed and did not execute.	RPC_S_CALL_FAILED_DNE
1728	A remote procedure call (RPC) protocol error occurred.	RPC_S_PROTOCOL_ERROR
1730	The transfer syntax is not supported by the RPC server.	RPC_S_UNSUPPORTED_TRANS_SYN
1732	The universal unique identifier (UUID) type is not supported.	RPC_S_UNSUPPORTED_TYPE
1733	The tag is invalid.	RPC_S_INVALID_TAG
1734	The array bounds are invalid.	RPC_S_INVALID_BOUND
1735	The binding does not contain an entry name.	RPC_S_NO_ENTRY_NAME
1736	The name syntax is invalid.	RPC_S_INVALID_NAME_SYNTAX
1737	The name syntax is not supported.	RPC_S_UNSUPPORTED_NAME_SYNTAX
1739	No network address is available to use to construct a universal unique identifier (UUID).	RPC_S_UUID_NO_ADDRESS
1740	The endpoint is a duplicate.	RPC_S_DUPLICATE_ENDPOINT
1741	The authentication type is unknown.	RPC_S_UNKNOWN_AUTHN_TYPE
1742	The maximum number of calls is too small.	RPC_S_MAX_CALLS_TOO_SMALL
1743	The string is too long.	RPC_S_STRING_TOO_LONG
1744	The RPC protocol sequence was not found.	RPC_S_PROTSEQ_NOT_FOUND
1745	The procedure number is out of range.	RPC_S_PROCNUM_OUT_OF_RANGE
1746	The binding does not contain any authentication information.	RPC_S_BINDING_HAS_NO_AUTH
1747	The authentication service is unknown.	RPC_S_UNKNOWN_AUTHN_SERVICE
1748	The authentication level is unknown.	RPC_S_UNKNOWN_AUTHN_LEVEL
1749	The security context is invalid.	RPC_S_INVALID_AUTH_IDENTITY
1750	The authorization service is unknown.	RPC_S_UNKNOWN_AUTHZ_SERVICE
1751	The entry is invalid.	EPT_S_INVALID_ENTRY
1752	The server endpoint cannot perform the operation.	EPT_S_CANT_PERFORM_OP
1753	There are no more endpoints available from the endpoint mapper.	EPT_S_NOT_REGISTERED
1754	No interfaces have been exported.	RPC_S_NOTHING_TO_EXPORT
1755	The entry name is incomplete.	RPC_S_INCOMPLETE_NAME
1756	The version option is invalid.	RPC_S_INVALID_VERS_OPTION
1757	There are no more members.	RPC_S_NO_MORE_MEMBERS
1758	There is nothing to unexport.	RPC_S_NOT_ALL_OBJS_UNEXPORTED

10/27/24,	12:23 PM WI	n32 - Error Codes (1000 - 1999)
1759	The interface was not found.	RPC_S_INTERFACE_NOT_FOUND
1760	The entry already exists.	RPC_S_ENTRY_ALREADY_EXISTS
1761	The entry is not found.	RPC_S_ENTRY_NOT_FOUND
1762	The name service is unavailable.	RPC_S_NAME_SERVICE_UNAVAILABLE
1763	The network address family is invalid.	RPC_S_INVALID_NAF_ID
1764	The requested operation is not supported.	RPC_S_CANNOT_SUPPORT
1765	No security context is available to allow impersonation.	RPC_S_NO_CONTEXT_AVAILABLE
1766	An internal error occurred in a remote procedure call (RPC).	RPC_S_INTERNAL_ERROR
1767	The RPC server attempted an integer division by zero.	RPC_S_ZERO_DIVIDE
1768	An addressing error occurred in the RPC server.	RPC_S_ADDRESS_ERROR
1769	A floating-point operation at the RPC server caused a division by zero.	RPC_S_FP_DIV_ZERO
1770	A floating-point underflow occurred at the RPC server.	RPC_S_FP_UNDERFLOW
1771	A floating-point overflow occurred at the RPC server.	RPC_S_FP_OVERFLOW
1772	The list of RPC servers available for the binding of auto handles has been exhausted.	RPC_X_NO_MORE_ENTRIES
1773	Unable to open the character translation table file.	RPC_X_SS_CHAR_TRANS_OPEN_FAIL
1774	The file containing the character translation table has fewer than 512 bytes.	RPC_X_SS_CHAR_TRANS_SHORT_FILE
1775	A null context handle was passed from the client to the host during a remote procedure call.	RPC_X_SS_IN_NULL_CONTEXT
1777	The context handle changed during a remote procedure call.	RPC_X_SS_CONTEXT_DAMAGED
1778	The binding handles passed to a remote procedure call do not match.	RPC_X_SS_HANDLES_MISMATCH
1779	The stub is unable to get the remote procedure call handle.	RPC_X_SS_CANNOT_GET_CALL_HANDLE
1780	A null reference pointer was passed to the stub.	RPC_X_NULL_REF_POINTER
1781	The enumeration value is out of range.	RPC_X_ENUM_VALUE_OUT_OF_RANGE
1782	The byte count is too small.	RPC_X_BYTE_COUNT_TOO_SMALL
1783	The stub received bad data.	RPC_X_BAD_STUB_DATA
1784	The supplied user buffer is not valid for the requested operation.	ERROR_INVALID_USER_BUFFER
1785	The disk media is not recognized. It cannot be formatted.	ERROR_UNRECOGNIZED_MEDIA
1786	The workstation does not have a trust secret.	ERROR_NO_TRUST_LSA_SECRET
1787	The SAM database on the Windows NT Server does not have a computer account for this workstation trust relationship.	ERROR_NO_TRUST_SAM_ACCOUNT
1788	The trust relationship between the primary domain and the trusted domain failed.	ERROR_TRUSTED_DOMAIN_FAILURE
1789	The trust relationship between this workstation and the primary domain failed.	ERROR_TRUSTED_RELATIONSHIP_FAILURE
1790	The network logon failed.	ERROR_TRUST_FAILURE
1791	A remote procedure call is already in progress for this thread.	RPC_S_CALL_IN_PROGRESS
1792	An attempt was made to logon, but the network logon service was not started.	ERROR_NETLOGON_NOT_STARTED
1793	The user's account has expired.	ERROR_ACCOUNT_EXPIRED
1794	The redirector is in use and cannot be unloaded.	ERROR_REDIRECTOR_HAS_OPEN_HANDLES
1795	The specified printer driver is already installed.	${\tt ERROR_PRINTER_DRIVER_ALREADY_INSTALLED}$
1796	The specified port is unknown.	ERROR_UNKNOWN_PORT
1797	The printer driver is unknown.	ERROR_UNKNOWN_PRINTER_DRIVER

1799 1800 1801 1802	The print processor is unknown. The specified separator file is invalid. The specified priority is invalid. The printer name is invalid. The printer already exists. The printer command is invalid. The specified datatype is invalid.	ERROR_UNKNOWN_PRINTPROCESSOR ERROR_INVALID_SEPARATOR_FILE ERROR_INVALID_PRIORITY ERROR_INVALID_PRINTER_NAME ERROR_PRINTER_ALREADY_EXISTS ERROR_INVALID_PRINTER_COMMAND
1800 1801 1802	The specified priority is invalid. The printer name is invalid. The printer already exists. The printer command is invalid. The specified datatype is invalid.	ERROR_INVALID_PRIORITY ERROR_INVALID_PRINTER_NAME ERROR_PRINTER_ALREADY_EXISTS
1801 1802	The printer name is invalid. The printer already exists. The printer command is invalid. The specified datatype is invalid.	ERROR_INVALID_PRINTER_NAME ERROR_PRINTER_ALREADY_EXISTS
1802	The printer already exists. The printer command is invalid. The specified datatype is invalid.	ERROR_PRINTER_ALREADY_EXISTS
	The printer command is invalid. The specified datatype is invalid.	
1000	The specified datatype is invalid.	ERROR INVALID PRINTER COMMAND
1803	•	
1804		ERROR_INVALID_DATATYPE
1805	The environment specified is invalid.	ERROR_INVALID_ENVIRONMENT
1806	There are no more bindings.	RPC_S_NO_MORE_BINDINGS
	The account used is an interdomain trust account. Use your global user account or local user account to access this server.	ERROR_NOLOGON_INTERDOMAIN_TRUST_ACCOUNT
9	The account used is a computer account. Use your global user account or local user account to access this server.	ERROR_NOLOGON_WORKSTATION_TRUST_ACCOUNT
9	The account used is a server trust account. Use your global user account or local user account to access this server.	ERROR_NOLOGON_SERVER_TRUST_ACCOUNT
;	The name or security ID (SID) of the domain specified is inconsistent with the trust information for that domain.	ERROR_DOMAIN_TRUST_INCONSISTENT
	The server is in use and cannot be unloaded.	ERROR_SERVER_HAS_OPEN_HANDLES
	The specified image file did not contain a resource section.	ERROR_RESOURCE_DATA_NOT_FOUND
	The specified resource type cannot be found in the image file.	ERROR_RESOURCE_TYPE_NOT_FOUND
	The specified resource name cannot be found in the image file.	ERROR_RESOURCE_NAME_NOT_FOUND
	The specified resource language ID cannot be found in the image file.	ERROR_RESOURCE_LANG_NOT_FOUND
	Not enough quota is available to process this command.	ERROR_NOT_ENOUGH_QUOTA
1817	No interfaces have been registered.	RPC_S_NO_INTERFACES
1818	The remote procedure call was canceled.	RPC_S_CALL_CANCELED
	The binding handle does not contain all required information.	RPC_S_BINDING_INCOMPLETE
	A communications failure occurred during a remote procedure call.	RPC_S_COMM_FAILURE
1821	The requested authentication level is not supported.	RPC_S_UNSUPPORTED_AUTHN_LEVEL
	No principal name registered.	RPC_S_NO_PRINC_NAME
	The error specified is not a valid Windows RPC error code.	RPC_S_NOT_RPC_ERROR
	A UUID that is valid only on this computer has been allocated.	RPC_S_UUID_LOCAL_ONLY
1825	A security package specific error occurred.	RPC_S_SEC_PKG_ERROR
1826	Thread is not canceled.	RPC_S_NOT_CANCELED
1827	Invalid operation on the encoding/decoding handle.	RPC_X_INVALID_ES_ACTION
	Incompatible version of the serializing package.	RPC_X_WRONG_ES_VERSION
1829	Incompatible version of the RPC stub.	RPC_X_WRONG_STUB_VERSION
	The RPC pipe object is invalid or corrupted.	RPC_X_INVALID_PIPE_OBJECT
	An invalid operation was attempted on an RPC pipe object.	RPC_X_WRONG_PIPE_ORDER
1832	Unsupported RPC pipe version.	RPC_X_WRONG_PIPE_VERSION
1898	The group member was not found.	RPC_S_GROUP_MEMBER_NOT_FOUND
	The endpoint mapper database entry could not be created.	EPT_S_CANT_CREATE

10/27/24,	12:23 PM Wi	n32 - Error Codes (1000 - 1999)
1900	The object universal unique identifier (UUID) is the nil UUID.	RPC_S_INVALID_OBJECT
1901	The specified time is invalid.	ERROR_INVALID_TIME
1902	The specified form name is invalid.	ERROR_INVALID_FORM_NAME
1903	The specified form size is invalid.	ERROR_INVALID_FORM_SIZE
1904	The specified printer handle is already being waited on	ERROR_ALREADY_WAITING
1905	The specified printer has been deleted.	ERROR_PRINTER_DELETED
1906	The state of the printer is invalid.	ERROR_INVALID_PRINTER_STATE
1907	The user must change his password before he logs on the first time.	ERROR_PASSWORD_MUST_CHANGE
1908	Could not find the domain controller for this domain.	ERROR_DOMAIN_CONTROLLER_NOT_FOUND
1909	The referenced account is currently locked out and cannot be logged on to.	ERROR_ACCOUNT_LOCKED_OUT
1910	The object exporter specified was not found.	OR_INVALID_OXID
1911	The object specified was not found.	OR_INVALID_OID
1912	The object resolver set specified was not found.	OR_INVALID_SET
1913	Some data remains to be sent in the request buffer.	RPC_S_SEND_INCOMPLETE
1914	Invalid asynchronous remote procedure call handle.	RPC_S_INVALID_ASYNC_HANDLE
1915	Invalid asynchronous RPC call handle for this operation.	RPC_S_INVALID_ASYNC_CALL
1916	The RPC pipe object has already been closed.	RPC_X_PIPE_CLOSED
1917	The RPC call completed before all pipes were processed.	RPC_X_PIPE_DISCIPLINE_ERROR
1918	No more data is available from the RPC pipe.	RPC_X_PIPE_EMPTY
1919	No site name is available for this machine.	ERROR_NO_SITENAME
1920	The file cannot be accessed by the system.	ERROR_CANT_ACCESS_FILE
1921	The name of the file cannot be resolved by the system.	ERROR_CANT_RESOLVE_FILENAME
1922	The entry is not of the expected type.	RPC_S_ENTRY_TYPE_MISMATCH
1923	Not all object UUIDs could be exported to the specified entry.	RPC_S_NOT_ALL_OBJS_EXPORTED
1924	Interface could not be exported to the specified entry.	RPC_S_INTERFACE_NOT_EXPORTED
1925	The specified profile entry could not be added.	RPC_S_PROFILE_NOT_ADDED
1926	The specified profile element could not be added.	RPC_S_PRF_ELT_NOT_ADDED
1927	The specified profile element could not be removed.	RPC_S_PRF_ELT_NOT_REMOVED
1928	The group element could not be added.	RPC_S_GRP_ELT_NOT_ADDED
1929	The group element could not be removed.	RPC_S_GRP_ELT_NOT_REMOVED