


WORKFLOW & ROLE ACCESS REFERENCE

Delta Migration Readiness Tracker

A step-by-step guide to how a server moves through the tracker — from sign-in to a completed Delta migration — with the exact View / Edit / Submit / Approve access each role has at every step, and the actual forms involved.

Internal reference document · CloudFuze Migration Team

Workflow Flowchart



9. Delta Migration Initiated

Access: automatic, once all 3 approve

Notifies → MIGRATION_ENGINEER (executes)

Available at any point (not part of the main path):

- Log / Resolve Escalation Ticket – Access: ALL
- Manage Access (add/remove users) – Access: ADMIN only
- Sign-off Contacts directory – View: ALL · Edit: ADMIN only

Roles: ADMIN · MIGRATION_MANAGER · DEV_LEAD · QA_LEAD · MIGRATION_ENGINEER — **ALL** means any of the five, once signed in and approved for access.

Roles in this application

Role	Shorthand used below
Admin	ADMIN
Migration Manager	MIGRATION_MANAGER
Dev Lead	DEV_LEAD
QA Lead	QA_LEAD
Migration Engineer	MIGRATION_ENGINEER

ALL means any of the five roles above, once signed in and approved for access. Access tags below use: **VIEW** (read-only), **CREATE**, **EDIT**, **SUBMIT**, **APPROVE**, **ADMIN** (Admin-only action), **AUTO** (system-triggered, no user).

The Workflow — Step by Step

1 Sign in

Sign in with a Microsoft work account.

VIEW ALL — must be an @cloudfuze.com address already added by an Admin

2 Dashboard & Projects

View the readiness overview and the list of existing projects.

VIEW ALL

3 Create or select a Project

Before anything can be imported, check whether a Project already exists for this name + product type (Message / Email / Content). If not, create it first.

VIEW ALL

CREATE ALL

Form — Create a Project

PROJECT NAME *

PROD-MIGRATION-01

PRODUCT TYPE *

Select... (Message / Email / Content) ▾

Create

4 Import Servers + Workspace Pairs (CSV)

Import server and workspace-pair data into the selected Project. Import stays disabled until a Project is selected in Step 3.

SUBMIT ADMIN, MIGRATION_MANAGER, MIGRATION_ENGINEER

Form — Import servers + workspace pairs from CSV

IMPORT INTO PROJECT

PROD-MIGRATION-01 ▾

CSV FILE

Choose file...

Expected columns: server_name, source_email, source_path, destination_email, destination_path, combination

Example row: PROD-MIGRATION-01, jane.doe@source-tenant.com, /jane.doe/My Drive, jane.doe@company.com, /sites/migrated/jane.doe, Google Drive → OneDrive

Upload & Import

5 Assign a Migration Manager

Every server needs an owner before its Pre-Check can be reviewed.

EDIT ALL — setting it for the first time

ADMIN ADMIN only — changing it after it's already set

Form — Set Migration Manager (per server)

SELECT PERSON

EMAIL (IF OTHER)

Select... / Other (type email) ▾

name@example.com

Set

6 Pre-Check Form

The checklist where migration readiness is actually verified — one shared form per server.

VIEW ALL — read-only for roles that can't edit

EDIT MIGRATION_ENGINEER, MIGRATION_MANAGER — status, notes, evidence per item

SUBMIT MIGRATION_ENGINEER, MIGRATION_MANAGER — only once every item has a status and evidence attached

Form — Pre-Check checklist

OneTime Migration

Completed ▾

Delta Type

Final delta ▾

Pre Delta Migration

Completed ▾

Data Verified

Completed ▾

Permissions Verified

Completed ▾

Hyperlinks Verified

Completed ▾

Workspace Status Updated in DB

Completed ▾

Drive changes

Not up to date ▾

 Each item (except Delta Type) requires an attached evidence file before submission.

Submit for Migration Manager Review

7 Request Sign-off

Nominate one person for each of the three sign-off roles.

SUBMIT ADMIN, MIGRATION_MANAGER, DEV_LEAD, QA_LEAD

Form — Request Sign-off

MIGRATION MANAGER

DEV LEAD

QA LEAD

Send for Approval

8 Approve Sign-off

Each nominated person approves their own role — matched by their login email. No one can approve on someone else's behalf.

APPROVE only the exact person nominated (who must also hold ADMIN, MIGRATION_MANAGER, DEV_LEAD, or QA_LEAD)

Approval status (per role)

Migration Manager — Pending, jane.doe@cloudfuze.com

Approve

Dev Lead — Approved by john.dev@cloudfuze.com

✓

QA Lead — Pending, priya.qa@cloudfuze.com

Approve

The "Approve" button only appears for the person whose login email matches the nominee.

9 Delta Migration Initiated

Once all three roles have approved, the server is automatically marked ready.

AUTO system-triggered — no user action. Notifies MIGRATION_ENGINEER to run the actual migration.

Available at any point (not part of the main path)

Log or resolve an Escalation ticket

SUBMIT ALL — fully manual, at any time

Form — Log a Ticket

SERVER	TICKET NO.	STATUS
Select server... ▾	JIRA-1042	Open ▾
DESCRIPTION		
Description of the ticket		
REASON		
Reason		
Log Ticket		

Manage Access (add/remove users, set roles)

ADMIN ADMIN only

Form — Add or update a user

EMAIL	ROLE
name@cloudfuze.com	Migration Engineer / Migration Manager / Dev Lead / QA Lead / Admin ▾
Add / Update	

Sign-off Contacts directory

VIEW ALL

ADMIN ADMIN only — add / remove contacts

Form — Add or update a contact

ROLE	NAME	EMAIL
Migration Manager / Dev Lead / QA Lead ▾	Name (as shown in dropdown)	name@cloudfuze.com
Add / Update		

NOTE — Escalation tickets are entirely manual in the current build. There is no automatic ticket creation anywhere in the backend; anyone signed in can log or resolve one at any time.

Quick reference: feature access matrix

Feature	ADMIN	MIGRATION MANAGER	DEV LEAD	QA LEAD	MIGRATION ENGINEER
Dashboard / Projects / Servers / Workspace Pairs (view)	Yes	Yes	Yes	Yes	Yes
Create a Project	Yes	Yes	Yes	Yes	Yes
Import Servers + Pairs (CSV)	Yes	Yes	No	No	Yes
Assign Migration Manager (first time)	Yes	Yes	Yes	Yes	Yes
Change Migration Manager	Yes	No	No	No	No
Pre-Check — view	Yes	Yes	Yes	Yes	Yes
Pre-Check — fill in / submit	No	Yes	No	No	Yes
Escalations — log / resolve	Yes	Yes	Yes	Yes	Yes
Sign-off — view status	Yes	Yes	Yes	Yes	Yes
Sign-off — request / nominate	Yes	Yes	Yes	Yes	No
Sign-off — approve	If nominated	If nominated	If nominated	If nominated	No
Approvals dashboard — view	Yes	Yes	Yes	Yes	Yes
Manage Access (users)	Yes	No	No	No	No
Sign-off Contacts — edit	Yes	No	No	No	No