

SOFLE v2 · ONE-PAGE LAYER CHEATSHEET

Colemak-DH · Bilateral Home-Row Mods · Semantic F13–F24 Protocol · 60 Positions · 2x Rotary Encoders

☐ Layer Access / Transition

 Transparent / Fallthrough

☐ Unused on this Layer

BASE										BASE - L0 (Colemak-DH)									
`	1	2	3	4	5						6	7	8	9	0	Del			
Esc	Q	W	F	P	B						J	L	U	Y	'	Bsp			
MEDIA	A Cmd	R Alt	S Ctrl	T Shift	G						M	N RShift	E RCtrl	I RAlt	O RCmd	;			
Shift Sticky	Z	X	C	D	V	Caps Word	Mute	K	H	,	.	/	RShift						
Cmd	Alt	Esc MOUSE	Space NAV	Tab HOST						Enter SYM	Bsp NUM	Del FUN	RAlt	RCmd					

[illegible]

MOUSE MOUSE · L2 (Hold L-thumb Esc)

The diagram shows a standard computer mouse layout with the following buttons labeled:

- Left Hand (L2):** L-thumb (Esc), L-Index, L-Middle, L-Ring, L-Pinky, L-Thumb, L-Index, L-Middle, L-Ring, L-Pinky.
- Right Hand:** R-Thumb, R-Index, R-Middle, R-Ring, R-Pinky, R-Thumb, R-Index, R-Middle, R-Ring, R-Pinky.
- Central Buttons:** Cmd, Alt, Ctrl, Shift.
- Mouse Buttons:** Redo, Paste, Copy, Cut, Undo, Back, Pointer (left, down, up, right), Forward, Scroll (left, down, up, right), Right click, Left click, Middle click.

[illegible][illegible]

Diagram illustrating the keyboard layout for typing "SYM L5" (Hold R-thumb Enter) using the QWERTY keyboard. The keys are arranged in rows, with the highlighted keys (SYM, L5, and the Enter key) shown in dashed boxes to indicate the sequence of presses.

Highlighted keys (dashed boxes):

- Row 1: SYM (Left Shift), L5 (Left Shift), and the Enter key (Right Shift).
- Row 2: ! (Left Shift), < (Left Shift), > (Left Shift), [(Left Shift), { (Left Shift), ((Left Shift).
- Row 3: & (Left Shift), | (Left Shift), * (Left Shift), - (Left Shift), = (Left Shift), + (Left Shift).
- Row 4: \ (Left Shift), / (Left Shift), and the Enter key (Right Shift).

Diagram illustrating the standard 104-key QWERTY keyboard layout. The layout is shown in two rows. The top row includes keys for FUN, L6 (Hold R-thumb Del), and various function keys (F12-F9, PrtSc, F11-F4, F5-F6, ScrLk, F10-F3, Pause, and navigation keys). The bottom row includes Caps Lock, RShift, RCtrl, RAlt, RCmd, and other navigation keys. The diagram is used to illustrate the placement of the R-thumb Del key.

The diagram illustrates the HOST keyboard layout, specifically the top row of keys. The layout is divided into two main sections: the left section for the left hand and the right section for the right hand. The left section includes keys for 'HOST', 'L7', and 'L-Thumb Tab'. The right section includes keys for 'R-Thumb Tab', 'Esc', and various function keys like 'Resize', 'Service', 'Focus', 'Move', 'Full', 'Prev WS', 'Float', and 'Next WS'. The diagram shows the physical arrangement of the keys and the corresponding labels for each key.

ADJUST ADJUST - L9 (Hold NAV + NUM)

The diagram shows the ADJUST keypad layout. The keypad is a 4x6 grid. The first row contains buttons: **BOOT** (red border), RESET, BT Clear, Out USB, Out BLE, Ext On. The second row contains: Ext Off, BT Next, BT Prev, **GAME** (red border), RESET, **BOOT** (red border). The third row contains: BT 1, BT 2, BT 3, BT 4, BT 5, and a dashed box containing a down arrow. The fourth row contains: a dashed box containing a down arrow, a dashed box containing a down arrow, and four empty dashed boxes. The fifth row contains: a dashed box containing a down arrow, a dashed box containing a down arrow, and four empty dashed boxes. The sixth row contains: a dashed box containing a down arrow, a dashed box containing a down arrow, and four empty dashed boxes.

ACCESS & SYSTEM NOTES		Layer Transitions & Recovery	
LAYER ACCESS		SPECIAL MECHANICS	
● MEDIA	Hold LMS	ADJUST	
		NAV + NUM conditional rule (L1+L4)	
● MOUSE	Hold L-thumb Esc (LH2)	GAME	
		Entered via ADJUST RT3 (&to L_GAME)	
● NAV	Hold L-thumb Space (LH1)	EXIT GAME	
		Right Encoder press REC (&to L_BASE)	
● HOST	Hold L-thumb Tab (LH0)	NUMBER ROW	
		Dedicated physical numbers on BASE/GAME	
● SYM	Hold R-thumb Enter (RH0)		
● NUM	Hold R-thumb Bsp (RH1)		
● FUN	Hold R-thumb Del (RH2)		
● ADJUST	Hold NAV + NUM (Space+Bsp)		
		HARDWARE RECOVERY	
		BOOTLOADER SHORTCUTS	
		Left side: NAV LT5 / ADJUST LT5	
		Right side: NUM RT5 / ADJUST RT5	
		Peripheral Bootloader Caveat	
		Right BOOT requires split link. Use physical reset button if unlinked.	

ENCODERS & PROTOCOL		EC11 Rotary Knobs & Host HID
LEFT ENCODER (LEC)	RIGHT ENCODER (REC)	HOST PROTOCOL (F13–F24)
ROTATION BEHAVIORS Default / NAV: Page Down / Page Up MEDIA layer: Previous / Next track MOUSE layer: Volume Down / Vol Up	ROTATION BEHAVIORS Default / NAV: Volume Down / Vol Up MOUSE layer: Page Down / Page Up	CROSS-PLATFORM HID F13–F17: Workspaces 1–5 Shift+F13..F17: Move to WS Ctrl+F13..F16: Directional Focus F21–F24: Copy / Paste / Cut / Undo
PUSH SWITCH (LEC) BASE: Caps Word toggle GAME: None (disabled)	PUSH SWITCH (REC) BASE: Mute toggle GAME: Exit to BASE (&to L_BASE)	Host Bridge Dependency Requires active Karabiner or AHK bridge.