打印机表

```
id
打印机名称
打印机类型
USER
UKEY
打印机编号
打印机 key
```

```
1
    -- Table structure for printer
 2
    -- ------
 3
    DROP TABLE IF EXISTS `printer`;
4
    CREATE TABLE `printer` (
 5
 6
       id int(11) NOT NULL AUTO_INCREMENT COMMENT 'ID',
7
       `printer_name` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_unicode_ci NU
     LL DEFAULT NULL COMMENT '打印机名称',
       `printer_type` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_unicode ci NU
     LL DEFAULT NULL COMMENT '打印机类型',
      `user` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_unicode_ci NULL DEFAU
9
     LT NULL COMMENT 'USER',
      `ukey` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_unicode_ci NULL DEFAU
10
     LT NULL COMMENT 'UKEY',
       `printer number` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4 unicode ci
11
     NULL DEFAULT NULL COMMENT '打印机编号',
       `printer_key` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_unicode_ci NUL
12
     L DEFAULT NULL COMMENT '打印机KEY',
       `status` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4 unicode ci NULL DEF
13
    AULT '启用' COMMENT '状态',
      `business id` int(11) NULL DEFAULT NULL COMMENT '商家ID',
14
      PRIMARY KEY (`id`) USING BTREE
15
16
     ) ENGINE = InnoDB AUTO_INCREMENT = 1 CHARACTER SET = utf8mb4 COLLATE = utf8mb4_un
     icode_ci COMMENT = '打印机表' ROW_FORMAT = DYNAMIC;
17
```