



Before you start: close Nuke, NukeStudio and Hiero. If they are open the installation may fail or be left halfway through.

Automatic installation

Extract the whole `.zip` into any folder. The installer and the `LGA_ToolPack-Layout` folder have to stay together.

Windows

- Double-click `installer_win.bat`.

macOS

- Open Terminal in the folder where you extracted the `.zip`.
- Run:

```
bash installer_mac.sh
```

- The leading `bash` is deliberate: `.sh` files lose their executable permission while travelling inside the `.zip`, so `./installer_mac.sh` would fail with *Permission denied*.

What the installer does

- Checks that no Foundry applications are running.
- Copies the pack to `~/ .nuke/LGA_ToolPack-Layout` (on Windows, `%USERPROFILE%\ .nuke`). If it cannot find the `.nuke` folder, it lets you enter another path.
- If a previous version was installed, it renames it to `LGA_ToolPack-Layout_backup` and offers to delete it at the end.
- Adds the required line to `init.py`, saving a numbered backup into `~/ .nuke/LGA_init_backups/` beforehand, named after the pack that made it.

Manual installation

If you would rather do it by hand, or the installer fails:

- Copy the `LGA_ToolPack-Layout` folder into `~/ .nuke` (`%USERPROFILE%\ .nuke` on Windows), so that you end up with `~/ .nuke/LGA_ToolPack-Layout/` holding `menu.py`, `py/` and everything else.
- With a text editor, add this line to the `init.py` file inside the `.nuke` folder:

```
nuke.pluginAddPath(' ./LGA_ToolPack-Layout')
```

Enabling and disabling tools

The pack lets you enable or disable each tool by editing the `_LGA_LayoutToolPack_Enabled.ini` file. They all default to `True`; the ones switched to `False` are hidden and skip loading altogether.

To keep your configuration across updates, copy that `.ini` into the `~/ .nuke/` folder. If both exist, the one in `~/ .nuke/` takes precedence.

Full documentation for every tool, and updates, at github.com/legandrop/LGA_ToolPack_Layout-for_Nuke