Field Name	Description
Element	Specify the element name in this prompt.
Format	An element name is 1 to 4 characters in length. If an element name is specified (not blank) for an element, the element mark is displayed as an asterisk (*) followed by the element name. It is not an asterisk (*) followed by the element type and three-digit sequence number. Specifies the printing direction of the text. Specify one of the following values:
	Horizontal
	Characters are printed from left to right.
	Vertical Characters are printed vertically from top to bottom. Vertical lines of text are printed from left to right.
	Vertical, right to left Characters are printed vertically from top to bottom. Vertical lines of text are printed from right to left, as the Japanese traditional way of formatting. This is the same meaning as Vertical when there is only one line of text. This choice appears when you are using DBCS data in the file for which you specified Y (Yes) for the <i>User specified DBCS data</i> prompt. The Right to Left option does not apply on a non-DBCS system. See on page 262 for examples of formatting.
	Notes:
	 You can enter only one line of text for a text element. To enter multiple lines of text, use a box element or multiple text elements. Not all printers support the vertical format. You cannot enter 2 (Vertical) or 3 (Vertical right to left) if the printer does not support the vertical format.
	3. To use 2=Vertical or 3=Vertical right to left, you should be aware of the following:
	• If your printer type is 1, you cannot use these formats.
Degree of rotation Color	 If your printer type is 2 or 3, you must specify font type 2 or 3. If your printer type is one of the others, no restrictions apply. Specifies the degrees of rotation of the text in terms of an angle measured clockwise from the overlay, page layout, or record layout. The default value is 0. Specifies the color used to print the text. The default value is *DEFAULT; the printer default color.
	Notes:
	1. Not all printers support color printing. You cannot enter a value in the <i>Color</i> prompt if the printer does not support color printing.
	If the printer does not support the color you select, an error occurs or a default color is used when this text is printed. You should check which colors are supported on the printer.
	3. To use values other than *DEFAULT and 8=Black, you should be aware of the following:
	• Your printer type must be 1 or 9, and your printer must be able to print the specified color.