Subroutines: abstraction and its implementation

3.2.1-3.2.2, 9.1,9.2, 9.3

Subroutine

- An abstraction
- Parameter passing
- Implementation of subroutine on a physical machine

Subroutine: abstraction

- Subroutine is a natural abstraction we use everyday
- Example Beef steak recipe

Ingredients

1 small onion, chopped / 7 cloves garlic / 1/2 cup olive oil / 1/2 cup vinegar / 1/2 cup soy sauce / 2 tablespoons chopped fresh rosemary / 2 tablespoons Dijon-style prepared mustard / 2 teaspoons salt / 1 teaspoon black pepper / 1 (2 pound) tri-tip steak

Directions

- Place onion, garlic, olive oil, vinegar, soy sauce, rosemary, mustard, salt, and pepper into the bowl of a food processor. Process until smooth. Place steak in a large resealable plastic bag. Pour marinade over steaks, seal, and refrigerate for about 3 hours.
- Preheat the grill for high heat.
- Brush grill grate with oil. Discard marinade, and place steak on the prepared grill. Cook for 7 minutes per side, or to desired doneness.

- Example collect mail
 - Tell the clerk you come to pick you your mail
 - (The clerk will get the mail and pass it to you)
- In these examples you abstract away the details from "high level of actions". At the abstract level, you only care about what the actions do.

- When to solve computational problems, we need a lot of such abstractions to
 - help us organize our thoughts and program.
 - Reduce the size of the program.

- Subroutine is such an abstraction
- You have subroutines in almost every program.

Subroutine

Subroutine

- Has name, parameters (and possibly return value)
 - A subroutine that returns a value is called a function.
 - A subroutine that does not return a value is called a procedure.
- Call (use) a subroutine
 - parameters in the call are actual parameters.
- Define a subroutine
 - Parameters in the definition are formal parameters.

Use/define subroutine

• Example: square of a number

Parameter passing

- A parameter can be declared as
 - Pass-by-value
 - Value of the actual parameter is copied to formal parameter, when calling a function
 - Pass-by-result
 - Value of the formal parameter is copied back to the actual parameter after the function returns
 - Pass-by-value-result
 - Value of actual parameter -> formal parameter, when calling, and value of formal parameter -> actural parameter after the function returns
 - Pass-by-reference
 - The actual parameter and the formal one have the same reference
 - Pass-by-name
 - Every time a formal parameter is used, the actual parameter will be reevaluated

Pass by value vs reference vs valueresult

Example

```
int m=9, i=5;
foo(m);
print(m);
proc foo(int b) {
 b := b + 5
```

Pass by name

```
array A[1..100] of int;
int i=5;
foo(A[i], i);
print A[i];
#print A[6] whose value is 7
#GOOD example
proc foo(name B, name k) {
 k=6;
  B = 7;
#text sub does this
proc foo{
  i = 6;
 A[i] = 7;
```

Return values for functions

One way to use the function name

```
function add_five ( value1 : integer ) : integer;
begin
   add_five := value1 + 5;
end;
```

Another way: using return

Discussion

- When the parameter is a big "object"
- Variable length of parameters
 - prinf("%s%s%s", x, y, z)
- A function can return a function in C.

Implementation

- How to implement subroutines on a physical machine?
 - Call a subroutine
 - Control should be transferred to the subroutine
 - Parameters should be passed to the subroutine
 - After the subroutine is done, the control should be returned
 - Define a subroutine
 - Depending on how "call a subroutine" is processed

Example

```
int m=9, i=5;
foo(m, 5);
print(m);

proc foo(int m, int n) {
  int x[12];
    m := m+5;
    n := m + n;
}
```

- Implementation of call/def subroutine
 - Major difficulty is the binding of local variables
 - If no recursion is allowed
 - Use static memory is alright
 - Otherwise
 - Use the stack memory

- Implementation details on call subroutine calling sequence
 - Push a new frame onto the stack. The frame contains
 - The values of the actual parameter
 - Save the frame pointer (fp)
 - bookkeeping information such as return address
 - "Jump" to the address of the subroutine
 - After the subroutine "returns", restore fp and pop out the frame
 - More details on stack layout can be found in Fig 9.2 of book. However, the calling sequence here is different from the one in the book.

- Implementation details of defining subroutine
 - Using fp to access the parameters and local variables
 - After the subroutine is finished, "jump" to the return address stored in the current frame of the stack

Example

 Implementation of the following code including call sequence and subroutine definition.

```
int m=9, i=5;
foo(m);
print(m);

proc foo(int b) {
    b := b+5
}
```

Summary

- Subroutine is a way of abstraction which helps solve complex problems
- Subroutine can be elegantly implemented on a physical machine by using the stack memory.