Практическая работа 16

```
Model revision number: C0
Motherboard revision number: A0
Model number: WS-CSwitch-PT
System serial number: FHK0610Z0WC

Cisco Internetwork Operating System Software
IOS (tm) PT3000 Software (PT3000-I6Q4L2-M), Version 12.1(22)EA4, RELEASE SOFTWARE (fcl)
Copyright (c) 1986-2006 by cisco Systems, Inc.
Compiled Fri 12-May-06 17:19 by pt_team

Press RETURN to get started!


%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

%LINK-5-CHANGED: Interface FastEthernet1/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/1, changed state to up


Switch>en
Switch#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#hostname lsw
lsw(config)#int vlan 1
lsw(config-if)#no sh

lsw(config-if)#
%LINK-5-CHANGED: Interface Vlan1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up

lsw(config-if)#ip address 192.168.0.2 255.255.255.0
lsw(config-if)#exit
lsw(config)#
```

Copy   Paste

Switch2 — □ ✕

Physical Config CLI Attributes

IOS Command Line Interface

```
Motherboard assembly number: 73-5781-09
Power supply part number: 34-0965-01
Motherboard serial number: FOC061004SZ
Power supply serial number: DAB0609127D
Model revision number: C0
Motherboard revision number: A0
Model number: WS-CSwitch-PT
System serial number: FHK0610Z0WC

Cisco Internetwork Operating System Software
IOS (tm) PT3000 Software (PT3000-I6Q4L2-M), Version 12.1(22)EA4, RELEASE SOFTWARE (fc1)
Copyright (c) 1986-2006 by cisco Systems, Inc.
Compiled Fri 12-May-06 17:19 by pt_team

Press RETURN to get started!


%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up


Switch>en
Switch#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Switch(config)#hostname lsw
lsw(config)#int vlan 1
lsw(config-if)#no sh

lsw(config-if)#
%LINK-5-CHANGED: Interface Vlan1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up

lsw(config-if)#ip address 192.168.0.3 255.255.255.0
lsw(config-if)#exit
lsw(config)#
```

```
lsw(config-if)#ip address 192.168.0.2 255.255.255.0
lsw(config-if)#exit
lsw(config)#line vty 0 4
lsw(config-line)#pass 111
lsw(config-line)#enable secret 123
lsw(config)#
```

PC1 — □ ✕

Physical   Config   Desktop   Programming   Attributes

Command Prompt   X

```
Cisco Packet Tracer PC Command Line 1.0
C:\>telnet 192.168.0.3
Trying 192.168.0.3 ...Open


User Access Verification

Password:
1sw>en
Password:
Password:
1sw#
```