

1a.



```
GRUB_DEFAULT=0
GRUB_TIMEOUT_STYLE=hidden
GRUB_TIMEOUT=10
GRUB_DISTRIBUTOR=`lsb_release -i -s 2> /dev/null || echo Debian`
GRUB_CMDLINE_LINUX_DEFAULT="quiet splash"
GRUB_CMDLINE_LINUX=""
```

```
if [ "x${is_top_level}" = xtrue ] && [ "x${GRUB_DISABLE_SUBMENU}" != xtrue ]; then
  linux_entry "${OS}" "${version}" simple \
    "${GRUB_CMDLINE_LINUX} ${GRUB_CMDLINE_LINUX_DEFAULT}"
```

```
if [ -z "${LONGNAME}" ] ; then
    LONGNAME="${LABEL}"
fi
```

```
ubu-elopez@ubuelopez-VirtualBox:~$ ls -l /etc/grub.d | grep 30_os-prober
-rwxr-xr-x 1 root root 13369 dic 18 2022 30_os-prober
ubu-elopez@ubuelopez-VirtualBox:~$
```

/etc/Default/grub→Aquest fitxer conte la configuració general de grub. Segons d'espera quin SISTEMA OPERATIU s'inicialitza per defecte, el background o si es buscant altres sistemes operatius.

```
GRUB_DEFAULT=0
GRUB_TIMEOUT_STYLE=hidden
GRUB_TIMEOUT=10
GRUB_DISTRIBUTOR=`lsb_release -i -s 2> /dev/null || echo Debian`
GRUB_CMDLINE_LINUX_DEFAULT="quiet splash"
GRUB_CMDLINE_LINUX=""
```

/etc/grub.d/10_linux→Aqui es on modificabem el text que es mostra a la entrada de Linux.

Tambe on podem deshabilitar que es mostri el mode recuperació i les opcions avançades.

```
if [ "x${is_top_level}" = xtrue ] && [ "x${GRUB_DISABLE_SUBMENU}" != xtrue ]; then
    linux_entry "${OS}" "${version}" simple \
    "${GRUB_CMDLINE_LINUX} ${GRUB_CMDLINE_LINUX_DEFAULT}"
```

/etc/grub.d/30_os-prober→Es on es modifica el text que es mostra a la entrada d'altres sistemes .

```
if [ -z "${LONGNAME}" ] ; then
    LONGNAME="${LABEL}"
fi
```

/etc/grub.d/20_memtest86+→Revocant el permis d'execucio a aquest fitxer ens treu la entrada de memtest al menu de grub.

```
ubu-elopez@ubuelopez-VirtualBox:~$ ls -l /etc/grub.d | grep 30_os-prober
-rwxr-xr-x 1 root root 13369 dic 18 2022 30_os-prober
ubu-elopez@ubuelopez-VirtualBox:~$
```

```
GNU nano 6.2 /etc/default/grub *
# If you change this file, run 'update-grub' afterwards to update
# /boot/grub/grub.cfg.
# For full documentation of the options in this file, see:
# info -f grub -n 'Simple configuration'

GRUB_DEFAULT=0
GRUB_TIMEOUT_STYLE=hidden
GRUB_TIMEOUT=15
GRUB_DISTRIBUTOR=`lsb_release -i -s 2> /dev/null || echo Debian`
GRUB_CMDLINE_LINUX_DEFAULT="quiet splash"
GRUB_CMDLINE_LINUX=""
```


GNU GRUB version 2.06

*Ubuntu

Advanced options for Ubuntu
Memory test (memtest86+.elf)
Memory test (memtest86+.bin, serial console)
Windows 10 (on /dev/sda1)

Use the ↑ and ↓ keys to select which entry is highlighted.
Press enter to boot the selected OS, 'e' to edit the commands
before booting or 'c' for a command-line.
The highlighted entry will be executed automatically in 15s.

1c



1d

GNU GRUB version 2.06

*Ubuntu Examen NF1

Advanced options for Ubuntu

Memory test (memtest86+.elf)

Memory test (memtest86+.bin, serial console)

2a

The image shows two side-by-side screenshots of user management windows. The left window, titled "Create New User", has a subtitle "Create a new user". It contains fields for "Name:" (with "ironman" entered) and "Username:" (with "ironman" in a dropdown menu). A blue information icon is next to a note: "Username must consist of: > lower case letters from the English alphabet > digits > any of the characters '.', ',', '-' and '_'". At the bottom are "Cancel" and "OK" buttons. The right window, titled "Change User Password", has a subtitle "Changing user password for: ironman" and a user icon. It has two radio buttons: "Set password by hand" (selected) and "Generate random password". Under "Set password by hand" are "New password:" and "Confirmation:" fields, both with masked text. Under "Generate random password" is a "Password set to:" field and a "Generate" button. At the bottom is a checkbox "Don't ask for password on login" and "Cancel" and "OK" buttons.

Repetim això per la resta d'usuaris

2b

The image shows a "New group" window. It has a subtitle "Basic Settings". It contains fields for "Group name:" (with "marvel" entered) and "Group ID:" (with "1010" and minus/plus buttons). Below is a "Group Members" section with a list box containing "mysticat" and "spiderman", with "spiderman" selected. At the bottom are "Cancel" and "OK" buttons.

Es repeteix l'acció per el grup dc


2c

The image shows a "Change Advanced User Settings" window. It has a subtitle "Changing advanced settings for: spiderman" and a user icon. It has three tabs: "Contact Information", "User Privileges", and "Advanced" (selected). Under the "Advanced" tab is a section "Advanced Settings" with a checkbox "Disable account". Below are fields for "Home directory:" (with "/home/spiderman" entered), "Shell:" (with "/bin/bash" in a dropdown), "Main group:" (with "marvel" in a dropdown), and "User ID:" (with "1001" and minus/plus buttons). At the bottom are "Cancel" and "OK" buttons.


Repetim l'accio per als usuaris ironman i mystica, i cambian marvel per dc als usuaris flash, Superman i Batman.

2d

2e



2f



3a

Sudo adduser --ingroup pawpatrol chase

Cambiem el nom chase per els usuaris: Marshall, rocky, skye, rex

3b

Sudo adduser Everest

Sudo adduser liberty

Sudo adduser Everest pinkpower

Sudo adduser liberty pinkpower

Sudo adduser skye pinkpower

3c

Sudo passwd -l rex

3d

Sudo usermod -e 2026-05-22 chase

3e

Sudo cat /etc/group

3f

/bin/bash al arxiu /etc/passwd

3g

Sudo cat /etc/passwd | grep root