
Development Environment

Lecturer: Eugene Lee



- ✓ Login to the terminal & Change Password
- ✓ Upload/Download Files Through FTP
- Set DISPLAY Environment
- ✓ Basic Operations
- ✓ On-line Text Editor VIM
- √ Text Editor notepad++
- Discussion Board



Login to the terminal

- ✓ Download, PUTTY, PIETTY, or any other telnet software, MobaXterm: PCMAN, ...
 - download MobaXterm here (hete/)
 - download PUTTY <u>here</u>
 (<u>http://www.chiark.greenend.org.uk/~sgtatham/putty/download.html</u>)
 - download PIETTY here (http://ntu.csie.org/~piaip/pietty/)
- ✓ Open PUTTY (or PIETTY)
 - >ee??.ee.nctu.edu.tw (number ?? may start from 01 to 05)
 - >linux??.ee.nctu.edu.tw (number ?? may start from 01 to 35)
- ✓ For information security, it is necessary to change the password of your account ASAP!
- Use the command
 - >passwd



Login to the terminal: MobaXterm

√ http://mobaxterm.mobatek.net/



MobaXterm Home/Professional Editions features comparison


Features	Personal Edition	Professional Edition
Installation/Uninstallation support	❤	₩
X server support	₩	₩
Remote computing clients	₩	₩
Advanced options	₩	₩
Logo customization	-	₩
Start up message modification	-	₩
Profile script customization	-	₩
Default options modification	-	₩
Professional support	-	₩
Access to plugins development	-	₩
MSI installer creation	-	₩
Silent (unattended) deployment	-	₩
Maximum number of saved sessions	12	unlimited
Maximum number of saved SSH tunnels	2	unlimited
Maximum number of saved macros	4	unlimited
Maximum run-time for TFTP service	60s	unlimited
Maximum run-time for FTP service	60s	unlimited
Maximum run-time for HTTP service	60s	unlimited
Games removal	-	enabled
Screensaver removal	-	enabled
Lifetime right to use	₩	₩
	Free download	VISA DISCUSSI BANK Subscribe now



Login to the terminal: MobaXterm

✓ Remote Host location: linux01~linux35, ee01 ~ ee05

e.g: ee05.ee.nctu.edu.tw






Login to the terminal: MobaXterm

✓ Account: iclab01~70

✓ Default Password:

iclab






Upload/Download Files: FileZilla

✓ With a FTP (File Transfer Protocol) software

- Login to ee??.ee.nctu.edu.tw series workstations.
- Download / Upload files as usual.
- FileZilla





Upload/Download Files: Terminal

With a terminal

Use ftp ee??.ee.nctu.edu.tw to enter the main directory of your

account.


```
1. /home/mobaxtem ×
                       • MobaXterm Personal Edition v7.1 •
                   (Unix utilities and X-server on Gnu/Cygwin)
       ➤ Your computer drives are accessible through the /drives path
       ➤ Your DISPLAY is set to 140.113.225.160:0.0
       ➤ When using SSH, your remote DISPLAY is automatically forwarded
       ➤ Each command status is specified by a special symbol (✓ or 🗶)
       Important:
       This is MobaXterm Personal Edition. The Professional edition
       allows you to customize MobaXterm for your company; you can add
       your own logo, your parameters, your welcome message and generate
       either an MSI installation package or a portable executable.
       We can also modify MobaXterm or develop the plugins you need.
       For more information: <a href="http://mobaxterm.mobatek.net/versions.php">http://mobaxterm.mobatek.net/versions.php</a>
[DeAn.DeAn-PC] ➤ ftp ee03.ee.nctu.edu.tw
Connected to ee03.ee.nctu.edu.tw.
220 (vsFTPd 2.2.2)
Name (ee03.ee.nctu.edu.tw:DeAn): iclabta01
331 Please specify the password.
Password:
Remote system type is UNIX.
Using binary mode to transfer files.
ftp>
ftp>
ftp>
ftp>
ftp> ls
200 PORT command successful. Consider using PASV.
150 Here comes the directory listing.
             3 484001 484
drwxr-xr-x
                                        4096 Sep 12 11:28 2015 iclab
-rw-r--r--
                          484
                                        4193 Aug 20 12:37 CDS.log
drwxr-xr-x
              5 484001
                                        4096 Aug 10 02:38 CH6 ex
drwxr-xr-x
                          484
                                        4096 Aug 10 05:54 DVEfiles
drwxr-xr-x
                          484
                                        4096 Sep 13 04:14 Desktop
              2 484001
                                        4096 Sep 13 04:14 Documents
                          484
drwxr-xr-x
              2 484001
drwxr-xr-x
              2 484001
                          484
                                        4096 Sep 13 04:14 Downloads
-rw-r--r--
              1 484001
                          484
                                        366 Sep 11 05:25 INF.sv
               3 484001
                          484
                                        4096 Aug 05 07:36 LEC06_PTT
drwxr-xr-x
drwxr-xr-x
              4 484001
                          484
                                        4096 Aug 24 09:14 Lab05
              5 484001
                          484
                                        4096 Sep 11 05:53 Lab09 EXERCISE
drwxr-xr-x
```



Upload/Download Files: Terminal

With a terminal

- Use get to download files and put to upload files.
- Use bye to logout.





If not using MobaXterm: Set DISPLAY Environment

- ✓ When using GUI tools such as nWave, nLint, IC Compiler,..., it's necessary to transmit the GUI windows from the workstation to your PC.
- ✓ If you're using MobaXterm, then execute the tool directly
- ✓ Open Xming
 - download Xming here
- ✓ >setenv DISPLAY 140.113.xxx.xxx:0
- Open the GUI tool



Linux: Basic Operations

- ✓ >man COMMAND //format and display the on-line manual pages
 - ex: man ln
- ✓ >mkdir DIRECTORY //make directory
 - e.g. mkdir –p /home/test
- ✓ >cd DESTINATION //change current directory
 - e.g. cd ../iclab08/Lab01/
 - e.g. cd (change to home directory)
- ✓ >cp SOURCE DESTINATION //copy files
 - e.g. cp ABC.v DEF.v
 - e.g. cp -rf Lab01/ Lab02/
- ✓ >mv SOURCE DESTINATION //move or rename files
 - e.g. mv ABC.v ../ABC.v
 - e.g. mv ABC.v DEF.v




Linux: Basic Operations

- ✓ >rm FILE_NAME //remove (delete) files
 - e.g. rm ABC.v
 - e.g. rm –rf Lab01/
- ✓ >Is //list directory contents
 - e.g. ls –l
 - or you can use *dir* as well.
- ✓ >In TARGET LINK_NAME //make links between files
 - e.g. ln –s ~iclabt01/LIB/slow.db slow.db
- ✓ >quota //display disk usage and limits
 - e.g. quota



- ✓ >vi filename //create a file
 - e.g. vi test.v
 - e.g. vim test.v





Command mode

- Move cursor:
 - [Page Down], [Page Up]
 - [Home], [End]
 - ↑↓←→: move cursor
 - G: cursor moves to last column
 - nG: "n" is number. cursor moves to "n"th column
 - gg: cursor moves to the first column. (=1G)
 - n<Enter>: "n" is number. cursor moves down n columns.
- Search & Replace:
 - /word: search for "word"
 - n: search the next
 - N: search the previous



- Delete & Copy & Paste:
 - [delete] or x: delete the character under the cursor.
 - X: delete the character before the cursor.
 - dd: delete a column where the cursor located at.
 - ndd: "n" is number. delete "n" columns.
 - yy: copy a column where the cursor located at.
 - nyy: "n" is number. copy "n" columns.
 - u: recover.
 - .: repeat the previous action.
 - [Shift]+v: select the column where the cursor located at.
 - [Ctrl]+v+[Shift]+I : edit multi-line.



✓ Insert mode:

- i : switch to insert mode before the current position.
- [Esc]: switch from the insert mode to the command mode


✓ Visual mode:

- :w : write the current buffer to disk.
- :q : closes current window.
- :wq: write the current buffer to disk and closes current window.
- :q!: closes current window forcibly.
- :set nu : display the column number.




Text Editor – notepad++

https://notepad-plus-plus.org/






Text Editor – notepad++





Text Editor – notepad++



Discussion board

https://www.facebook.com/groups/547755475584158/

