

Change of Authorization (CoA):


The RADIUS Change of Authorization (CoA) feature provides a mechanism to change the attributes of an Authentication, Authorization, and Accounting (AAA) session after it is authenticated. When a policy changes for a user or user group in AAA, administrators can send the RADIUS CoA packets from the AAA server such as a Cisco ISE to reinitialize authentication and apply the new policy. Change of authorization (CoA) is a method by which authorization changes can be performed dynamically after the device or user is authenticated.

Enable Change of Authorization


```
SW1(config)#aaa server radius dynamic-author
```

```
SW1(config-locsvr-da-radius)#client 192.168.169.200 server-key test123
```

```
SW1(config-locsvr-da-radius)#exit
```



```
aaa server radius dynamic-author  
client 10.1.1.1 server-key test123
```



Implement CoA:

- o Profiling requires CoA to change the authorization state of an endpoint.
- o Cisco ISE allows a global configuration to issue a Change of Authorization (CoA).
- o Enables profiling service with more control over endpoints already authenticated.
- o After profiler CoA is enabled globally, CoA is automatically sent for any endpoint.
- o CoA sent for any endpoint that transitions from unknown to any known profile.
- o **No CoA (default)**-Use this option to disable the global configuration of CoA.
- o **Port Bounce**-Use this option, if the switch port exists with only one session.
- o Port Bounce CoA shuts down switch port & performs no shutdown to reenale it.
- o **Reauth**-Use this option to enforce reauthentication of already authenticated endpoint.
- o If the port exists with multiple sessions, then use the Reauth CoA option.
- o Change of Authorization (CoA) can be enable Per-profile as well.

To modify or change this service, navigate to **Administration>Setting>Profiling**

The screenshot shows the Cisco Identity Services Engine (ISE) Administration console. The navigation pane on the left has 'Profiling' highlighted. The main content area is titled 'Profiler Configuration'. It contains a dropdown menu for '* CoA Type:' with options: 'No CoA', 'No CoA', 'Port Bounce', and 'Reauth'. Below this are fields for 'Current custom SNMP community strings:' and 'Change custom SNMP community strings:', both with a 'Show' button. At the bottom, there is a field for 'Confirm changed custom SNMP community strings:' with a 'Show' button. The 'Administration' and 'Settings' tabs in the top navigation bar are highlighted.

To modify per-profile, navigate to **Policy>Profiling>Profiling Policies** Click on any profile there is **associated CoA Type**

The screenshot shows the Cisco Identity Services Engine (ISE) Administration console. The navigation pane on the left has 'Profiling' highlighted, and 'Profiling Policies' is selected. The main content area is titled 'Profiler Policy List > Aastra-IP-Phone'. The 'Profiler Policy' configuration page for 'Aastra-IP-Phone' is shown. It includes fields for '* Name' (Aastra-IP-Phone), 'Policy Enabled' (checked), '* Minimum Certainty Factor' (10), '* Exception Action' (NONE), '* Network Scan (NMAP) Action' (NONE), 'Create an Identity Group for the policy' (No, use existing Identity Group hierarchy), '* Parent Policy' (Aastra-Device), and '* Associated CoA Type' (Global Settings). The 'Associated CoA Type' dropdown menu is open, showing options: 'Global Settings', 'No CoA', 'Port Bounce', 'Reauth', and 'Global Settings'. The 'Rules' section is visible at the bottom.