


FortiADC Network Setup Lab:



Management Subnet	192.168.100.0/24
FortiGate Management IP	192.168.100.200
FortiADC Management IP	192.168.100.210
Internal Servers Subnet	192.168.1.0/24
FortiADC External Subnet	192.168.2.0/24
FortiGate Firewall External	100.0.1.0/24
FortiADC Internal IP Address	192.168.1.254
FortiADC External IP Address	192.168.2.1
FortiGate Firewall Internal IP	192.168.2.254
FortiGate Firewall External IP	100.0.1.254
SRV1 IP Address	192.168.1.1
SRV2 IP Address	192.168.1.2
SRV3 IP Address	192.168.1.3
SRV3 IP Address	192.168.1.4
Virtual Sever-1	192.168.2.100
Virtual Sever-2	192.168.2.200
FortiGate VIP-1	100.0.1.100
FortiGate VIP-2	100.0.1.200
External PC1 IP Address	100.0.1.1
External PC2 IP Address	100.0.1.2
External PC3 IP Address	100.0.1.3

Outside Interface Configuration

```
FortiADC # config system interface
FortiADC (interface) # edit port2
FortiADC (port2) # set allowaccess ping
FortiADC (port2) # set ip 192.168.2.1/24
FortiADC (port2) # end
```

Inside Interface Configuration

```
FortiADC # config system interface
FortiADC (interface) # edit port3
FortiADC (port3) # set allowaccess ping
FortiADC (port3) # set ip 192.168.1.254/24
FortiADC (port3) # end
```

Default Routing Configuration

```
FortiADC # config router static
FortiADC (static) # edit 1
FortiADC (1) # set destination 0.0.0.0/0
FortiADC (1) # set gateway 192.168.2.254
FortiADC (1) # end
```

Log in to the FortiADC GUI, navigate to **Network > Interface**. Locate the interface you want to configure.

The screenshot shows the FortiADC GUI. On the left sidebar, 'Network' is highlighted in blue, and 'Interface' is selected. The main content area shows the 'Interface' configuration page. At the top, there are tabs for 'Interface' (selected) and 'Overlay Tunnel'. Below the tabs, there's a 'Management Interface' section with a 'Management Status' toggle. A 'Save' button and a 'Refresh' button are visible. Below this is a table of interfaces. The table has columns: Name, Type, IPv4/Netmask, and Availability. The rows are: port1 (Physical, 192.168.100.210/24, green up arrow), port2 (Physical, 0.0.0.0/0, green up arrow), port3 (Physical, 0.0.0.0/0, green up arrow), and port4 (Physical, 0.0.0.0/0, red down arrow). A red box highlights the rows for port2 and port3.

Name	Type	IPv4/Netmask	Availability
port1	Physical	192.168.100.210/24	↑
port2	Physical	0.0.0.0/0	↑
port3	Physical	0.0.0.0/0	↑
port4	Physical	0.0.0.0/0	↓

Click the **Edit** button, In the configuration window, set Allow Access, IPv4/Netmask. Click **OK** or Apply to save the changes.

Dashboard

Security Fabric

FortiView

System

Shared Resources

Network

Interface

Routing

NAT

QoS

Packet Capture

Server Load Balance

Link Load Balance

Interface

Name

port2

Status

Enabled

Disabled

Allow Access

☐ HTTPS
☒ Ping
☐ SSH
☐ SNMP
☐ HTTP
☐ Telnet

Type

Physical

Mode

Static

PPPoE

DHCP

Traffic Group

default

Floating

☐

Mode Specifics

IPv4/Netmask

192.168.2.1/24

Example: 192.0.2.5/24

IPv6/Netmask

::/0

Example: 2001:0db8:85a3::8a2e:0370:7334/64

Dashboard

Security Fabric

FortiView

System

Shared Resources

Network

Interface

Routing

NAT

QoS

Packet Capture

Server Load Balance

Link Load Balance

Interface

Name

port3

Status

Enabled

Disabled

Allow Access

☐ HTTPS
☒ Ping
☐ SSH
☐ SNMP
☐ HTTP
☐ Telnet

Type

Physical

Mode

Static

PPPoE

DHCP

Traffic Group

default

Floating

☐

Mode Specifics

IPv4/Netmask

192.168.1.254/24

Example: 192.0.2.5/24

IPv6/Netmask

::/0

Example: 2001:0db8:85a3::8a2e:0370:7334/64

	Name	Type	IPv4/Netmask	Availability	Allow Access
	port1	Physical	192.168.100.210/24	↑	HTTPS Ping SSH
	port2	Physical	192.168.2.1/24	↑	Ping
	port3	Physical	192.168.1.254/24	↑	Ping
	port4	Physical	0.0.0.0/0	↓	

FortiADC GUI, and then click **Network > Routing > Static**

Static Policy OSPF ISP BGP Access List Access IPv6 List

Delete Create New Add Filter

ID	Destination	Gateway
1	0.0.0.0/0	192.168.2.254

Showing 1 to 1 of 1 entries 0 rows selected Show 25 entries

FortiADC FortiADC

Static

Destination 0.0.0.0/0
Example: 192.0.2.5/24 2001:0db8:85a3::8a2e:0370:7334/64

Gateway 192.168.2.254
Example: 192.0.2.1 2001:0db8::1

Distance 10
Default: 10 Range: 1-255

Save Cancel

Static Policy OSPF ISP BGP Access List Access IPv6 List

Delete Create New Add Filter

ID	Destination	Gateway
1	0.0.0.0/0	192.168.2.254

Showing 1 to 1 of 1 entries 0 rows selected Show 25 entries