


Virtual Server Setup:



Management Subnet	192.168.100.0/24
FortiGate Management IP	192.168.100.200
FortiADC Management IP	192.168.100.210
Internal Servers Subnet	192.168.1.0/24
FortiADC External Subnet	192.168.2.0/24
FortiGate Firewall External	100.0.1.0/24
FortiADC Internal IP Address	192.168.1.254
FortiADC External IP Address	192.168.2.1
FortiGate Firewall Internal IP	192.168.2.254
FortiGate Firewall External IP	100.0.1.254
SRV1 IP Address	192.168.1.1
SRV2 IP Address	192.168.1.2
SRV3 IP Address	192.168.1.3
SRV3 IP Address	192.168.1.4
Virtual Sever-1	192.168.2.100
Virtual Sever-2	192.168.2.200
FortiGate VIP-1	100.0.1.100
FortiGate VIP-2	100.0.1.200
External PC1 IP Address	100.0.1.1
External PC2 IP Address	100.0.1.2
External PC3 IP Address	100.0.1.3

From the main menu, click **Server Load Balance > Virtual Server**. Click **Create New**

FortiADC FortiADC

- Dashboard >
- Security Fabric >
- FortiView >
- System >
- Shared Resources >
- Network >
- Server Load Balance** ✓

Virtual Server

Virtual Server Content Rewriting Content Routing NAT Source Pool

Delete + Create New Search

+ Add Filter

Name	Type	Address	Port
No			

Showing 0 to 0 of 0 entries 0 rows selected Show 25 entries

And then select **Advanced Mode** in the drop-down list.

Virtual Server Content Rewriting Content Routing NAT Source Pool Schedule Pool

Delete + Create New Search

+ Add Filter Basic Mode

Advanced Mode

Name	Type	Address	Port	Profile
------	------	---------	------	---------

Virtual Server

Basic General Security Monitoring

Name WEB-VS

Type Layer 7 Layer 4 Layer 2

Status Enable Disable Maintain

Address Type IPv4 IPv6

Traffic Group default

Comments Specify the comments

Specifics

Schedule Pool

Content Routing

Packet Forwarding Method DNAT

Save Cancel

Virtual Server

Basic

General

Security

Monitoring

Configuration

Address

192.168.2.100

Example: 192.0.2.1

Port

80

Default: 80 Range: 0 or 1-65535. You can specify up to eight ports or port ranges separated by space, e.g., 80-90 100. Valid values are from 0 to 65535, with 0 for Layer-4 virtual servers only.

Connection Limit

0

Default: 0 Range: 0-100000000 concurrent connections

Connection Rate Limit

0

Default: 0 (disabled) Range: 0-86400 connections per second

Interface

port2

Resources

Profile

LB_PROF_TCP

Persistence

Click to select.

Method

LB_METHOD_ROUND_ROBIN

Real Server Pool

WEB-Pool

Clone Pool

Click to select

Virtual Server

Basic

General

Security

Monitoring

Traffic Log

☒

Traffic logging should be used mainly for debugging; traffic logging will consume extensive memory and CPU resources. Please disable traffic logging after debugging is complete.

FortiView

☒

Save

Cancel

Virtual Server

Content Rewriting

Content Routing

NAT Source Pool

Schedule Pool

Clone Pool

🗑️ Delete

+ Create New ▾

Search

🔍

+ Add Filter

Name	Type	Address	Port	Profile	Status
WEB-VS	Layer 4	192.168.2.100	80	LB_PROF_TCP	Enable

Showing 1 to 1 of 1 entries

0 rows selected

Show 25 entries

From the main menu, click **Server Load Balance > Virtual Server**. Click **Create New** And then select **Advanced Mode** in the drop-down list.

Virtual Server	Content Rewriting	Content Routing	NAT Source Pool	Schedule Pool
Delete	+ Create New	Search		
Add Filter	Basic Mode			
	Advanced Mode			
Name	Type	Address	Port	Profile

Virtual Server

Basic

General

Security

Application Optimization

Monitoring

Name

SEC-VS

Type

Layer 7

Layer 4

Layer 2

Status

Enable

Disable

Maintain

Address Type

IPv4

IPv6

Traffic Group

default

Comments

Specify the comments

Specifics

Schedule Pool

Content Routing

Content Rewriting

NAT Source Pool List

Selected Items

<

>

Available Items

Create New

Transaction Rate Limit

0

Default: 0 (disabled) Range: 0-1048567 transactions per second

Virtual Server	
Basic General Security Application Optimization Monitoring	
Configuration	
Address	192.168.2.200 Example: 192.0.2.1
Port	80 Default: 80 Range: 0 or 1-65535. You can specify up to eight ports or port ranges separated by space, e.g., 80-90 100. Valid values are from 0 to 65535, with 0 for Layer-4 virtual servers only.
Connection Limit	0 Default: 0 Range: 0-100000000 concurrent connections
Interface	port2
Resources	
Profile	LB_PROF_HTTP
Persistence	Click to select.
Method	LB_METHOD_ROUND_ROBIN
Real Server Pool	SEC-Pool
Clone Pool	Click to select
Auth Policy	Click to select
Scripting	☐ To use scripts to manipulate compressed HTTP/HTTPS data body, you must have decompression rules configured first.

Virtual Server

Basic General Security Application Optimization **Monitoring**

Traffic Log ☒ Traffic logging should be used mainly for debugging; traffic logging will consume extensive memory and CPU resources. Please disable traffic logging after debugging is complete.

FortiView ☒

WCCP ☐

 **Save** **Cancel**

Finally, we have two Virtual Servers one Layer 4 and one Layer 7

WEB-VS	WEB-Pool, Layer 4
SEC-VS	SEC-Pool, Layer 7

Virtual Server							
Delete + Create New Search + Add Filter							
Name	Type	Address	Port	Profile	Status	Availability	
WEB-VS	Layer 4	192.168.2.100	80	LB_PROF_TCP	Enable	✓	
SEC-VS	Layer 7	192.168.2.200	80	LB_PROF_HTTP	Enable	✓	

Click **FortiView > Logical Topology**, and then observe the virtual server, real server pool, and real server topology map shown on the **Server Load Balance** tab

