


Layer 7 Virtual Server Setup:



Management Subnet	192.168.100.0/24
FortiGate Management IP	192.168.100.200
FortiADC Management IP	192.168.100.210
Internal Servers Subnet	192.168.1.0/24
FortiADC External Subnet	192.168.2.0/24
FortiGate Firewall External	100.0.1.0/24
FortiADC Internal IP Address	192.168.1.254
FortiADC External IP Address	192.168.2.1
FortiGate Firewall Internal IP	192.168.2.254
FortiGate Firewall External IP	100.0.1.254
SRV1 IP Address	192.168.1.1
SRV2 IP Address	192.168.1.2
SRV3 IP Address	192.168.1.3
SRV3 IP Address	192.168.1.4
Virtual Sever-1	192.168.2.100
Virtual Sever-2	192.168.2.200
FortiGate VIP-1	100.0.1.100
FortiGate VIP-2	100.0.1.200
External PC1 IP Address	100.0.1.1
External PC2 IP Address	100.0.1.2
External PC3 IP Address	100.0.1.3

From the main menu, click **Server Load Balance > Virtual Server**. Select the **WEB-VS** which is **Layer 4** double click to edit or click on pencil icon.

FortiADC FortiADC

Dashboard > Virtual Server Content Rewriting Content Routing NAT Source Pool Schedule Pool

Security Fabric > Delete + Create New Search

FortiView > Add Filter

System >

Shared Resources >

Network >

Server Load Balance > Virtual Server

Application Resources

Name	Type	Address	Port	Profile
WEB-VS	Layer 4	192.168.2.100	80	LB_PROF_TCP
SEC-VS	Layer 7	192.168.2.200	80	LB_PROF_HTTP

Showing 1 to 2 of 2 entries 0 rows selected Show 25 entries

In **Basic** setting lets change **Type Layer 4** to **Layer 7**

Virtual Server

Basic General Security Monitoring

Name WEB-VS

Type Layer 7 Layer 4 Layer 2

Status Enable Disable Maintain

Address Type IPv4 IPv6

Traffic Group default

Comments Specify the comments

In **Type** click on **Layer 7** to change.

Virtual Server

Basic General Security Application Optimization Monitoring

Name WEB-VS

Type Layer 7 Layer 4 Layer 2

Status Enable Disable Maintain

Address Type IPv4 IPv6

Traffic Group default

Comments Specify the comments

In **General** Tab make sure that the **Profile** is HTTP (**LB_PROF_HTTP**) and click **Save**.

Virtual Server

Basic

General

Security

Application Optimization

Monitoring

Configuration

Address

192.168.2.100

Example: 192.0.2.1

Port

80

Default: 80 Range: 0 or 1-65535. You can specify up to eight ports or port ranges separated by space, e.g., 80-90 100. Valid values are from 0 to 65535, with 0 for Layer-4 virtual servers only.

Connection Limit

0

Default: 0 Range: 0-100000000 concurrent connections

Interface

port2

Resources

Profile

LB_PROF_HTTP

Persistence

Click to select.

Method

LB_METHOD_ROUND_ROBIN

Real Server Pool

WEB-Pool

Clone Pool

Click to select

Auth Policy

Click to select

Finally, we have modified **Layer 4** Virtual Server to **Layer 7** Virtual Server.

Virtual Server

Content Rewriting

Content Routing

NAT Source Pool

Schedule Pool

Clone Pool

Delete

+ Create New

Search

+ Add Filter

Name	Type	Address	Port	Profile
WEB-VS	Layer 7	192.168.2.100	80	LB_PROF_HTTP
SEC-VS	Layer 7	192.168.2.200	80	LB_PROF_HTTP

Showing 1 to 2 of 2 entries
0 rows selected
Show 25 entries