Chapter 8

Mineral Resources

• Geologists divide mineral resources into two categories.

Metallic mineral resources include gold, copper, aluminum, iron, or other metals.

Nonmetallic mineral resources include building stone, gravel, sand, gypsum, phosphate, and salt, used in construction or for chemical production.

• What is a metal?

8.1 Metal

- Metals are opaque, shiny, and smooth solids that conduct electricity.
- These properties come from metallic bonds, in which electrons are delocalized free to move easily from atom to atom.
 - In contrast, covalent or ionic bonds in nonmetallic materials do not allow this kind of electron mobility.
- The behavior of a metal depends on:
 - The strength of bond between atoms;
 - The architecture of its crystal structure.
- Metals are also known for their mechanical properties:

Ductility the ability to be drawn into thin wires.

Malleability the ability to be hammered into thin sheets.

8.2 Discovery of Metals

8.2.1 Early Metals

Gold (ca. 6,000 BCE) likely the first humans encountered because it occurs naturally in pure (native) form.

Copper (ca. 5,000 BCE) first metal smelted from ores. Initially used in pure form, but too soft for durable tools.

Bronze (ca. 3,300 BCE) discovery of alloying copper with tin created bronze, which is stronger and harder. Marked a major leap in tool and weapon production, leading to the Bronze Age.

8.2.2 Iron Age

Iron (ca. 1,200 BCE) more abundant than copper and tin, but harder to smelt (requires higher temperatures). Compared with copper or bronze, iron offered greater strength, hardness, and abundance, eventually replacing bronze for tools, weapons, and building materials.

Steep (ca. BCE, widely used by $\sim 1,000$ CE) an alloy of iron and carbon, stronger and more versatile that pure iron.

Stainless steel (1,913 CE) alloy of iron with chromium, highly resistant to corrosion. Revolutionized modern engineering, especially in medicine, food, and infrastructure.

8.2.3 Modern Metals

Aluminum (1,825 CE) lightweight, corrosion-resistant; now essential for aviation, packaging, and construction.

Other 19th-20th Century Discoveries Include:

Titanium (1791) lightweight, strong, corrosion-resistant.

Uranium (1789) key for nuclear energy in the 20th century.

Rare Earths (1790s-1900s) a set of 17 nearly indistinguishable lustrous silvery-white soft heavy metals. Now critical for electronics and green energy.

- Scandium (Sc)
- Yttrium (Y)
- Cerium (Ce)
- Neodymium (Nd)
- Lanthanum (La)
- Dysprosium (Dy)
- Samarium (Sm)
- Terbium (Tb)
- Praseodymium (Pr)
- Gadolinium (Gd)

- Europium (Eu)
- Ytterbium (Yb)
- Holmium (Ho)
- Lutetium (Lu)
- Thulium (Tm)
- Erbium (Er)
- Promethium (Pm)

8.3 Native Metals

- Native metals (gold, silver, copper, iron) occur naturally in their pure, metallic form, rather than as part of a compound.
- Native metals are relatively rare in nature, which is why they are so valuable. In fact, native metals make up only a tiny fraction of the world's current metal supply.

8.4 Ore Minerals

- Naturally occurring minerals that contain a sufficient concentration of valuable elements, typically metals, to be extracted and processed.
- Ores are often associated with gangue minerals, which are non-valuable materials that need to be separated from the desired ore minerals.
- Principal metals in most common use today:
 - Aluminum from Bauxite
 - Iron from Hematite and Magnetite
 - Copper from Chalcopyrite
 - Zinc from Sphalerite
 - Lead from Galena

8.5 Smelting

- A high-temperature process that extracts a metal from its ore.
- When minerals decompose during smelting, the process yields a metal (useful product) and a nonmetallic residue known as slag.
- Different ores require different smelting techniques at varying temperatures.

8.5.1 Smelting vs Melting

- Melting involves heating a substance to its melting point, causing it to change from a solid to a liquid without a chemical change.
- Smelting is a more complex process that includes melting but also involves a chemical reaction to remove oxygen and separate the metal from impurities.

8.6 Ore-forming Processes

- Ore deposits typically require specialized geological processes to concentrate valuable metals or minerals into economically recoverable amounts.
 - Magmatic processes
 - Hydrothermal processes
 - Metamorphic processes
 - Sedimentary processes
- Whereas, other deposits form by more common geologic processes like erosion, deposition, or evaporation.
- c.e., metals and many useful minerals are typically present in the Earth's crust in very low concentrations. To make mining economical, nature must concentrate them far beyond their average abundance!

8.7 Ore Deposits

Magmatic process as magma cools, certain materials crystallize earlier or segregate into dense layers. This can concentrate metals like chromium, nickel, or platinum.

Hydrothermal process hot fluids dissolve metals, travel through fractures, and precipitate valuable minerals in veins when conditions (temperature, pressure, chemistry) change.

Metamorphic process metamorphism can remobilize and re-concentrate minerals under high pressure and temperature.

Sedimentary process metals like iron, manganese, or uranium can concentrate in chemical sedimentary rocks (e.g., banded iron formations).

- Banded iron formations (BIFs) consist of alternating layers of gray hematite (Fe_2O_3) and iron-rich red chert (jasper).
- \bullet Manganese nodules grow slowly on the sea floor and are rich in MnO_2 and trace elements.

8.8 Ore Exploration and Production

Prospecting geologists and prospectors look for visible traces of ore minerals in rock outcrops.

Geological surveys measurements of magnetism, gravity, or radioactivity can reveal anomalies in the Earth's field that may indicate hidden ore bodies.

Geochemical surveys soil, water, sediments, and even plants (biota) are analyzed.

Drilling and sampling once an ore deposit is suspected, geologists drill boreholes to collect subsurface rock samples. This helps determine the shape, size, and extent of the deposit.

Production (mining) the type of mining depends on the proximity of the ore body to the surface.

Open-pit mining used when ore bodies are close to the surface. It involves removing overburden and excavating the ore in large benches. This method is cheaper and safer.

Underground mining necessary for deeper ore bodies. It involves shafts and tunnels to access ore. Although it reaches greater depths, it is more expensive and hazardous, with risks like tunnel collapses, poisonous gases, and explosions.

8.9 Mining and Ore Processing

- Miners extract crude ore (yellow)
- Waste rock is often piled in waste rock dumps.
 - Not all rock removed contains valuable minerals.
 - Waste rock is the unmineralized or low-grade rock that must be separated and dumped.
- The crude ore is transported to processing facilities
- Ore goes to concentration and chemical separation ponds
 - Valuable minerals are separated from waste through flotation, leaching, or other chemical methods.
- After separation, the valuable portion is collected as concentrated metal.
- The leftover slurry of ground rock and processing chemicals is called tailings.
 - Tailings are stored in tailings ponds, often held back by dams to prevent them from flowing downstream.
 - These storage areas are major environmental concerns, as failures can release toxic material.

8.10 Mining and Environment

Mineral extraction and processing leaves significant ecological footprints.

8.10.1 Land disturbance

- Mining reshapes landscapes through open pits, waste dumps, and tailing ponds.
- Removal of vegetation and topsoil leads to erosion and loss of biodiversity.

8.10.2 Waste Rock and Tailings

- Waste rock piles may leach harmful chemicals, especially if they contain sulfide minerals (leading to acid mine drainage).
- Tailings pongs store toxic slurries of fine particles mixed with processing chemicals. Dam failures have caused catastrophic downstream destruction.

8.10.3 Water Pollution

- Acid Mine Drainage (AMD): When sulfide-rich waste reacts with water and oxygen, it produces sulfuric acid, dissolving heavy metals (like arsenic, lead, and mercury) into rivers and groundwater.
- Cyanide and mercury contamination from gold mining can poison ecosystems.

8.10.4 Air Pollution

- Dust from blasting, hauling, and crushing contributes to particulate air pollution.
- Smelting releases sulfur dioxide (SO₂), which can form acid rain.
- GHG from fuel use and processing add to climate change impacts.

8.11 Nonmetallic Rock and Mineral Resources

- Common nonmetallic resources are used in construction, agriculture, industry, and chemical processes.
 - e.g., limestone, crushed stone, granite, marble, gypsum, phosphate, pumice, clay, and, salt, and sulfur.
- Dimension stone: intact slabs and blocks of rock
 - e.g., granite, marble, limestone
 - Workers carefully cut rock from quarry walls to preserve intact pieces.

- Crushed stone (aggregate): broken rock used as raw material for cement, concrete, and asphalt.
- Concrete and mortar: rock-like mixtures made of aggregate (sand, gravel, or crushed rock) held together by cement.
- Cement is the powder that consists of lime (CaO), quartz (SiO_2) , aluminum oxide (Al_2O_3) , and iron oxide (Fe_2O_3) . It acts as the binder in concrete and mortar.
 - Natural cement was first developed by the Ancient Romans and is made from volcanic ash + limestone heated in kilns. Rarely produced today.
 - Portland cement is most common modern cement. It is made by carefully mixing crushed limestone, sandstone, and shale in correct proportions.

8.12 Nonmetallic Minerals for Homes and Farms

- Clay forms from the chemical weathering of silicate rocks. It is used for bricks, pottery, porcelain, and other ceramics.
- Quartz (silica) sourced from quartz sand (beach or sandstone). It forms glass and is also used in photovoltaic cells for solar panels.
- **Gypsum** mixed with water into a slurry and layered paper. It produces gypsum board (drywall) for building construction.

Plastics derives from oil extracted from underground reserves.

Asbestos come from serpentine, formed by the reaction of olivine with water. Asbestos was historically used for fireproofing and insulation.

8.13 How Long will Resources Last?

- Mineral resources are nonrenewable once an ore deposit or a limestone hill is mined, it's gone forever.
- Industrialized countries consume vast amounts of mineral resources each year.
- Strategic minerals are of particular concern: manganese, platinum, chromium, and cobalt. These metals are alloyed with iron to make special-purpose sheets (e.g., aerospace industry).