SMB Connect Quick Start

v0.7.5 (build 28) · 19 August 2026

1. Open SMB Connect

SMB Connect keeps a list of the important servers and shares you want to use, including an individual account for each share. It connects through your preferred fast network, such as `10GbE`, and can fall back to a slower network, such as `1GbE`, when that is better than having no connection.

For a regular Mac window, enable **Settings -> General -> Show Dock icon and desktop window**. The same app gains a Dock icon and resizable window while the menu-bar control stays available.

2. Complete Setup And Connect

1. Open `Settings... -> Shares`, choose a share, and confirm its Mount Name and network paths.
2. Save the username and password.
3. Press `Connect`, or use `Connect All` for every ready share.

Passwords stay in the user's Keychain.

3. Read The Status

A green check means mounted; `Fallback` means it used a slower configured path. Blue dashed means ready to connect. Grey means no endpoint answered. Yellow or red means complete setup or follow the card's repair guidance.

4. Make It Automatic

In **Settings -> General**, enable **Launch at login**, **Connect all shares on start**, and **Auto-reconnect dropped shares** for hands-off operation.

5. Preferred, Fallback, And Warnings

SMB Connect tries paths in priority order: `10GbE`, `1GbE`, then an optional VPN. Fallback is still connected. Quit apps before `Switch to Preferred...`.

If Wi-Fi conflicts with required `1GbE` or `10GbE` storage, turn Wi-Fi off before connecting so the Mac uses the intended wired path.

- **Name conflict or duplicate** - inspect `/Volumes` and follow the card's guided repair.
- **Mounted by Another User** - ask that user to eject or sign out.
- **Offline** - no endpoint is answering; check the server and network.

For support, choose **Help -> Export Logs and Diagnostics...**. The report omits passwords and account names.

6. CopyTrust Mount Requests

CopyTrust can request an approved volume before ingest using the same Mount Name model as the older Desktop app:

```
smbconnect://v1/mount?volume=Example_Archive&request=<uuid>
```

In **Settings -> Shares**, enable **Allow apps to request this volume**. The Mount Name must be unique and its credential already saved.

SMB Connect chooses the best endpoint, reads its Keychain entry, and mounts. CopyTrust waits for `/Volumes/Example_Archive`, then checks its required folder. It receives no password, server address, or network preference.

MDM can enforce `allowExternalMountRequests = true`; passwords remain per user and per Mac in Keychain.

7. SMB Connect Desktop Compatibility

The separate **SMB Connect Desktop** app is no longer needed for new installs. It remains compatible and sends the same request shown above, but does not read passwords; SMB Connect remains the mount and credential authority.

More Help

Open `?` Help or read the full User Guide.