SETS AI LEAD WATCHER (64-BIT WINDOWS)

DOCUMENT 1: HOW TO INSTALL THE SOFTWARE

Step-by-Step 64-Bit Windows Setup Wizard, PostgreSQL Setup & Android Phone Installation

1. Overview & System Requirements

SETS AI Lead & Building Permit Watcher is packaged into a self-contained 64-Bit Windows Setup Wizard (SETS_AI_Watcher_Setup_x64.exe). It checks prerequisites, verifies PostgreSQL connectivity, sets up all databases and multi-user profiles, and creates desktop shortcuts with the official SETS logo icon. Colleagues and team members do NOT need to install Python or manually configure code to run the software.

- Supported Operating System: Windows 10 or Windows 11 (64-Bit / x64 Architecture).

- Installer File to Share with Colleagues: SETS_AI_Watcher_Setup_x64.exe (located in installation package).
- Standalone Executable File: SETS_AI_Lead_Watcher_x64.exe (can also run directly without installation).
- Database Prior Requirement: PostgreSQL 14, 15, 16, or 18 (Local or Cloud like Neon.tech / Supabase). Checked in Step 1.

2. Step-by-Step Installation Using SETS_AI_Watcher_Setup_x64.exe

Double-click SETS_AI_Watcher_Setup_x64.exe on any 64-Bit Windows PC to launch the interactive Setup Wizard:

Step 1 of 4: Prior Requirement - PostgreSQL Database Verification

- Automated PostgreSQL Detection: The wizard immediately probes localhost port 5432 to check if PostgreSQL is already active and running.
- Option A: Existing / Cloud PostgreSQL URI: If you have a PostgreSQL database (local or free cloud like Neon.tech or Supabase), enter your connection URI and click 'Test Connection'.
- Option B: One-Click Auto-Install via Winget: Click 'Auto-Install PostgreSQL (winget)' to have Windows Package Manager download and install official 64-bit PostgreSQL silently.
- Option C: Official PostgreSQL Download: Click 'Download PostgreSQL' to open the official EnterpriseDB Windows installer if you prefer manual setup.

Step 2 of 4: Destination Directory & Desktop Icon Selection

- 64-Bit Architecture Verification: The installer confirms 64-bit Windows compatibility and DPAPI encryption capability.
- Installation Path: Accept the default path (C:\Users\<Name>\AppData\Local\Programs\SETS_AI_Lead_Watcher) or select a custom folder.
- Desktop Shortcut: Keep 'Create Desktop Shortcut with SETS Logo Icon' checked to pin the application with the SETS Shield icon.

Step 3 of 4: Automated Component & Multi-User Profile Installation

Click 'Install Now (Step-by-Step)' to begin the automated setup process:

```
[Step 1/6] Verifying 64-Bit OS & creating isolated target directories...
[Step 2/6] Installing SETS_AI_Lead_Watcher_x64.exe & SETS Logo Icon...
[Step 3/6] Initializing PostgreSQL Tables & Multi-User Isolated Vaults...
[Step 4/6] Setting up Open-Source WhatsApp Bridge & Web Search Frameworks...
[Step 5/6] Creating Desktop Shortcut ('SETS AI Lead Watcher') with SETS Logo...
[Step 6/6] Zero Preloaded Info Enforced: Clean slate profile ready!
```

Step 4 of 4: Finish & Launch Application

- Instant Launch: Click 'Finish & Launch SETS AI Lead Watcher'. The native SETS Control Center and the full dashboard interface will open automatically.

3. Clean Slate & Multi-User Profile Isolation Guarantee

The software enforces strict multi-user privacy and persistence:

- Zero Default Information: The app launches completely clean with NO preloaded demo leads, contacts, or hardcoded personal phone numbers.
- Profile Persistence: When a user logs in (e.g. 'Zakariya' or 'Engineer_1'), all their configured search areas, custom keywords, portal cookies, contacts, and tender enquiries persist and automatically pop up on their next launch.
- Complete Isolation: If a different colleague logs in with a different username, none of the previous user's data is displayed. Each user gets an independent, encrypted vault.

4. Setting Up Free WhatsApp Alerts (Optional)

To enable free automated background WhatsApp messages from your PC:

- Step 1: Double-click 'start_whatsapp_bridge.bat' in the installation folder (or click 'Start Open-Source WhatsApp Bridge' in the control window).
- **Step 2: A browser tab will open at http://127.0.0.1:3001 displaying a QR Code.**
- Step 3: On your phone, open WhatsApp -> Settings -> Linked Devices -> Link a Device, and scan the QR code on screen.
- Step 4: Once linked, the status badge turns green ('CONNECTED & READY') and the AI Watcher will automatically dispatch alerts to whatever phone numbers are configured in your Team Contacts tab!

5. Installing the Android Phone Application (.APK)

- Step 1 - Transfer APK: Send SETS_AI_Lead_Watcher_Android.apk to your Android phone via WhatsApp, USB, or Google Drive.
- Step 2 - Tap to Install: Tap the APK on your phone. If prompted, allow 'Install from this source' and confirm.
- Step 3 - Launch App: Open 'SETS AI Watcher' from your app drawer. It features phone-optimized bottom navigation, thumb-friendly buttons, and runs either autonomously offline or connected to your PostgreSQL server.