


License borrowing and license troubleshooting in Geomec 5.4

In Geomec we have three different licenses that we need to borrow:

1. Geomec
2. Open Inventor (the user interface):
 - a. OpenInventor
 - b. MeshVizXLM
3. Diana

From the “Settings” menu, “Borrow license”, you activate the dialog for borrowing licenses:




For Geomec and Open Inventor, adjust the borrow end date and press the “Request borrow” button.


The Geomec feature “GEOMECH_FULL” will be borrowed automatically. The Open Inventor features will only be borrowed when they are first requested and used, which happens during Geomec start-up. You need to exit Geomec, start Geomec and visualize a mesh in order to do this. We advise loading a small model and view some formations.

Once you have the features as shown in the above dialog, you should be okay.


For Diana, press “Request borrow Diana” which should open Internet Explorer:



If you don't see the “Detach” buttons, then go to the “Configuration” page, tab “Detachable licenses”:




Check the box with “Enable Detaching of Licenses” and press “Submit” and return to the “Products” page. Now “Detach” the “SLnet Diana 10.0” product, which takes you to the “Detach License” details page:



The “Detach Method” should be set to “**Online** Detach license from <some server> and automatically attach it to <your computer>”.

Now you can fill in the date, and “Submit”. If all went well, you see a success screen:



If you return to the “Products” page, there should be a “Local” entry for Diana.

You can now work offline. Please test Geomec by disconnecting it from the network, loading a small model and running a calculation and viewing some arbitrary things in the model.

If you didn't see any Diana licenses, or if Diana fails to retrieve licenses, then please go to the “Configuration” page again and select the tab “Access to Remote License Managers.”

Make sure that the field “Remote License Search Parameters” contains the address of your license server. Normally this is filled in on installation of Geomec. However, depending on your network, you may need a different address. Contact support to find out.

Returning the borrowed licenses is straight forward. The “Return current license early” button will return the Geomec and OIV licenses. The Diana license can be returned via the “Request borrow Diana” and then “Cancel License” the Local license.

Please note that Diana uses the borrowed license for validation, even if it is expired. You need to explicitly return expired borrowed licenses in order to use a new borrowed license, or to contact the license server for a live license check.


Troubleshooting.

This deals primarily with failing to start Geomec due to license issues.

Please make sure you have installed the latest version of the Shell “gift box”. You can find it on this page:


http://swwww.shell.com/it/itso/technical_landscape_services/technical_infrastructure/license_service/gls2.html

If Geomec still doesn't start, but shows this dialog:



The product mentioned may differ.

Press “OK”. If all is well, you will now see the following dialog:



Geomec can try two or three things, based on the OIV license settings it found. For this you need to press "Retry". Geomec will now stop, and you will have to restart it to actually do the attempt.

If all attempts fail, Geomec will start with attempt 1 again, so keep an eye out for that.

If one of the attempts succeeds, you can use Geomec, and next time it starts it will use these settings again.