

---(i)

Chapter 10 Differentiability Ex 10.1 Q10

Chapter 10 Differentiability Ex 10.1 Q10

Her,e
$$f(x) = \begin{cases} ax^2 - b & \text{, if } |x| < 1 \\ \frac{1}{|x|} & \text{, if } |x| \ge 1 \end{cases}$$

$$= \begin{cases} -\frac{1}{x} & \text{, if } x \le -1 \\ ax^2 - b & \text{, if } -1 < x < 1 \end{cases}$$

$$= \begin{cases} ax^2 - b & \text{, if } x \le -1 \end{cases}$$

$$= \begin{cases} ax^2 - b & \text{, if } x \le 1 \end{cases}$$
LHL $= \lim_{x \to 1^-} f(x)$

$$= \lim_{h \to 0} f(1 - h)$$

$$= \lim_{h \to 0} a(1 - h)^2 - b$$

$$= a - b$$
RHL $= \lim_{h \to 0} f(x)$

$$= \lim_{h \to 0} f(1 + h)$$

$$= \lim_{h \to 0} \frac{1}{1 + h}$$

$$= 1$$

Since, f(x) is continuous, so LHS = RHS a - b = 1

$$\begin{aligned} & \text{(LHD at } x = 1) = \lim_{x \to 1^-} \frac{f\left(x\right) - f\left(1\right)}{x - 1} \\ & = \lim_{h \to 0} \frac{f\left(1 - h\right) - 1}{1 - h - 1} \\ & = \lim_{h \to 0} \frac{a\left(1 - h\right)^2 - b - 1}{-h} \\ & = \lim_{h \to 0} \frac{a\left(1 - h\right)^2 - \left(a - 1\right) - 1}{-h} \end{aligned}$$
 Using equation (i),
$$& = \lim_{h \to 0} \frac{a + ah^2 - 2ah - a + 1 - 1}{-h} \\ & = \lim_{h \to 0} \frac{ah^2 - 2ah}{-h} \\ & = \lim_{h \to 0} (2a - ah) \\ & = 2a \end{aligned}$$

$$(\mathsf{RHD} \ \mathsf{at} \ \mathsf{x} = 1) = \lim_{x \to 1^+} \frac{f\left(x\right) - f\left(1\right)}{x - 1}$$

$$= \lim_{h \to 0} \frac{f\left(1 + h\right) - f\left(1\right)}{1 + h - 1}$$

$$= \lim_{h \to 0} \frac{\frac{1}{1 + h} - 1}{h}$$

$$= \lim_{h \to 0} \frac{1 - 1 - h}{(1 + h)h}$$

$$= \lim_{h \to 0} \frac{-1}{1 + h}$$

$$= -1$$

Since f(x) is differentiable at x = 1,

(LHD at
$$x = 1$$
) = (RHD at $x = 1$)
 $2a = -1$
 $a = \frac{-1}{2}$

Put
$$a = \frac{-1}{2}$$
 in equation (i),
 $a - b = 1$
 $\left(\frac{-1}{2}\right) - b = 1$
 $b = \frac{-1}{2} - 1$
 $b = \frac{-3}{2}$
 $a = \frac{-1}{2}$

******* END ******