


Configuring OSPF in cisco packet tracer  
Done By Samip Khadka



PC0

| Physical                   | Config | Desktop                                 | Programming | Attrib |
|----------------------------|--------|-----------------------------------------|-------------|--------|
| <b>IP Configuration</b>    |        |                                         |             |        |
| Interface                  |        | FastEthernet0                           |             |        |
| IP Configuration           |        |                                         |             |        |
| <input type="radio"/> DHCP |        | <input checked="" type="radio"/> Static |             |        |
| IPv4 Address               |        | 192.168.1.2                             |             |        |
| Subnet Mask                |        | 255.255.255.0                           |             |        |
| Default Gateway            |        | 192.168.1.4                             |             |        |
| DNS Server                 |        | 0.0.0.0                                 |             |        |

PC1

| Physical                   | Config | Desktop                                 | Programming | Attrib |
|----------------------------|--------|-----------------------------------------|-------------|--------|
| <b>IP Configuration</b>    |        |                                         |             |        |
| Interface                  |        | FastEthernet0                           |             |        |
| IP Configuration           |        |                                         |             |        |
| <input type="radio"/> DHCP |        | <input checked="" type="radio"/> Static |             |        |
| IPv4 Address               |        | 192.168.1.3                             |             |        |
| Subnet Mask                |        | 255.255.255.0                           |             |        |
| Default Gateway            |        | 192.168.1.4                             |             |        |
| DNS Server                 |        | 0.0.0.0                                 |             |        |

PC2

| Physical                   | Config | Desktop                                 | Programming | Attrib |
|----------------------------|--------|-----------------------------------------|-------------|--------|
| <b>IP Configuration</b>    |        |                                         |             |        |
| Interface                  |        | FastEthernet0                           |             |        |
| IP Configuration           |        |                                         |             |        |
| <input type="radio"/> DHCP |        | <input checked="" type="radio"/> Static |             |        |
| IPv4 Address               |        | 198.168.2.2                             |             |        |
| Subnet Mask                |        | 255.255.255.0                           |             |        |
| Default Gateway            |        | 198.168.2.4                             |             |        |
| DNS Server                 |        | 0.0.0.0                                 |             |        |

PC3

| Physical                   | Config | Desktop                                 | Programming | Attrib |
|----------------------------|--------|-----------------------------------------|-------------|--------|
| <b>IP Configuration</b>    |        |                                         |             |        |
| Interface                  |        | FastEthernet0                           |             |        |
| IP Configuration           |        |                                         |             |        |
| <input type="radio"/> DHCP |        | <input checked="" type="radio"/> Static |             |        |
| IPv4 Address               |        | 198.168.2.3                             |             |        |
| Subnet Mask                |        | 255.255.255.0                           |             |        |
| Default Gateway            |        | 198.168.2.4                             |             |        |
| DNS Server                 |        | 0.0.0.0                                 |             |        |

Router0

Physical Config CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

FastEthernet0/0

Port Status

On

Link Speed

100 Mbps

10 Mbps

Auto

Duplex

Half Duplex

Full Duplex

Auto

MAC Address

0003.E48C.0B01

IP Configuration

IPv4 Address

198.168.1.4

Subnet Mask

255.255.255.0

Tx Ring Limit

10

Router0

Physical Config CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

FastEthernet0/1

Port Status

On

Link Speed

100 Mbps

10 Mbps

Auto

Duplex

Half Duplex

Full Duplex

Auto

MAC Address

0003.E48C.0B02

IP Configuration

IPv4 Address

198.168.3.2

Subnet Mask

255.255.255.0

Tx Ring Limit

10

Router1

Physical Config CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

FastEthernet0/0

Port Status

On

Link Speed

100 Mbps

10 Mbps

Auto

Duplex

Half Duplex

Full Duplex

Auto

MAC Address

0002.4A27.2101

IP Configuration

IPv4 Address

198.168.2.4

Subnet Mask

255.255.255.0

Tx Ring Limit

10

Physical **Config** CLI Attributes

|                    |                 |  |
|--------------------|-----------------|--|
| <b>GLOBAL</b>      | FastEthernet0/1 |  |
| Settings           |                 |  |
| Algorithm Settings |                 |  |
| <b>ROUTING</b>     |                 |  |
| Static             |                 |  |
| RIP                |                 |  |
| <b>SWITCHING</b>   |                 |  |
| VLAN Database      |                 |  |
| <b>INTERFACE</b>   |                 |  |
| FastEthernet0/0    |                 |  |
| FastEthernet0/1    |                 |  |

|                  |                                                                                                                         |
|------------------|-------------------------------------------------------------------------------------------------------------------------|
| Port Status      | <input checked="" type="checkbox"/> On                                                                                  |
| Link Speed       | <input checked="" type="radio"/> 100 Mbps <input type="radio"/> 10 Mbps <input checked="" type="checkbox"/> Auto        |
| Duplex           | <input type="radio"/> Half Duplex <input checked="" type="radio"/> Full Duplex <input checked="" type="checkbox"/> Auto |
| MAC Address      | 0002.4A27.2102                                                                                                          |
| IP Configuration |                                                                                                                         |
| IPv4 Address     | 198.168.3.3                                                                                                             |
| Subnet Mask      | 255.255.255.0                                                                                                           |
| Tx Ring Limit    |                                                                                                                         |
|                  | 10                                                                                                                      |

Physical Config **CLI** Attributes

Router(config-if)#

Router con0 is now available

Press RETURN to get started.

```
Router>enable
Router#configure Terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router ospf 1
Router(config-router)#network 192.168.1.0 0.0.0.255 area 1
Router(config-router)#network 192.168.3.0 0.0.0.255 area 1
Router(config-router)#exit
Router(config)#
```

## Router1

Physical Config CLI Attributes

```
Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#

Router>
Router>enable
Router#configure Terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router ospf 2
Router(config-router)#network 192.168.2.0 0.0.0.255 area 1
Router(config-router)#network 192.168.3.0 0.0.0.255 area 1
Router(config-router)#exit
Router(config)#
```

## PC3

Physical Config Desktop Programming Attributes

### Command Prompt

```
C:\>ping 192.168.1.3

Pinging 192.168.1.3 with 32 bytes of data:

Reply from 192.168.1.3: bytes=32 time<1ms TTL=126
Reply from 192.168.1.3: bytes=32 time<1ms TTL=126
Reply from 192.168.1.3: bytes=32 time<1ms TTL=126
Reply from 192.168.1.3: bytes=32 time<1ms TTL=126

Ping statistics for 192.168.1.3:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

C:\>ping 192.168.1.2

Pinging 192.168.1.2 with 32 bytes of data:

Reply from 192.168.1.2: bytes=32 time<1ms TTL=126
Reply from 192.168.1.2: bytes=32 time<1ms TTL=126
Reply from 192.168.1.2: bytes=32 time<1ms TTL=126
Reply from 192.168.1.2: bytes=32 time<1ms TTL=126

Ping statistics for 192.168.1.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms
```