



DEVELOPER GUIDE

Ship licensing in 15 minutes.

Everything you need to protect, license, and sell your software — RSA-signed keys, machine activation, automatic delivery, and a native License Manager for your customers.

PrimeLock · v1.0 · for plugin & app developers

What is PrimeLock?

PrimeLock is a complete software licensing platform. When a customer buys your plugin or app, PrimeLock issues them an RSA-signed license key, emails it automatically, and lets them activate it on their machine through a free License Manager app. Your software verifies the signature locally — so once a customer is activated, your plugin works forever, even offline.

Why developers choose PrimeLock

- **No servers to run.** PrimeLock handles key generation, signing, delivery, and activation. You write five lines of code.
- **No hardware.** Unlike dongle-based systems, activation is software-only — nothing to ship, nothing to lose.
- **Built for African creators.** Works natively with Selar and Flutterwave, and any other store through a generic webhook.
- **Offline-friendly.** After the first activation, the signed token is verified locally. Your customers can work with no internet, forever.
- **Subscriptions & subscribe-to-own.** Perpetual, subscription, trial, and pay-to-own models are all supported out of the box.

The big picture

You do the setup once — about fifteen minutes. After that, every sale is fully automated: the customer pays, PrimeLock issues and emails the key, the customer activates, and your plugin unlocks. You just watch licenses appear in your dashboard.

The 15-minute setup

Five steps take you from zero to selling. Each one is shown in detail on the following pages.

1

Create your account

2 min

Sign up free at primelock.theprimis.org. The onboarding wizard guides you through everything below.

2

Register your product

1 min

PrimeLock generates a private RSA-2048 keypair automatically. The private key never leaves our servers.

3

Copy your integration details

30 sec

Grab your Product ID, public key, and webhook URL — all one-click copy from the product page.

4

Add the SDK to your plugin

10 min

Drop in two files, add five lines of C++. The SDK handles activation and verification.

5

Connect your store

1 min

Paste your webhook URL into Selar (or any platform). Sales now issue licenses automatically.

Steps 1–3 · Account & product

1 · Create your account

Go to primelock.theprimis.org and click **Get Started Free**. Enter your email, a password, and your name. You'll land directly in the onboarding wizard, which walks you through creating your first product and shows your keys.

The free plan includes 1 product and 50 licenses per month — plenty to launch with. You can upgrade any time as you grow.

2 · Register your product

Click **+ Add Product** and fill in:

- **Name** — the display name, e.g. "Track Namer"
- **Slug** — a URL-safe id, auto-filled, e.g. track-namer
- **Type** — plugin, desktop, web, or game

The moment you save, PrimeLock generates a dedicated **RSA-2048 keypair** for this product. The private key is stored encrypted on our servers and is used to sign license tokens. You never see it, so it can never leak from your side. The public key is yours to embed.

3 · Copy your integration details

Open the product page. Everything you need is at the top, each with a one-click copy button:

Field	Where it goes
Product ID	PRODUCT_ID in your plugin
RSA Public Key	PUBLIC_KEY in your plugin
Selar Webhook URL	Your Selar product's webhook settings
Generic Webhook URL	Gumroad, Paystack, Stripe — any platform

Step 4 · Add the SDK

The PrimeLock C++ SDK is two files — `primelock.h` and `primelock.cpp`. Download them from github.com/mannymusic000-afk/primelock-sdk and add them to your JUCE project (Projucer file list or CMake target sources).

Verify the license at startup

In your plugin's constructor, create a client with your Product ID, public key, and the API URL, then check whether this machine is activated:

```
#include "primelock.h"

const char* PRODUCT_ID = "your-product-uuid";
const char* PUBLIC_KEY = "-----BEGIN PUBLIC KEY-----\n...";
const char* API_URL    = "https://api.primelock.theprimis.org";

PrimeLock::Client license(PRODUCT_ID, PUBLIC_KEY, API_URL);

if (! license.isActivated())
    showLicenseScreen(); // your own activation UI
```

What the SDK handles for you

- RSA-2048 signature verification of the license token — entirely offline.
- Machine fingerprinting, so a key binds to a limited set of machines.
- Secure token storage in the OS keychain / application support folder.
- Activation, deactivation, and background re-validation calls.
- Grace periods, expiry, and seat-limit handling.

Link OpenSSL

The SDK uses OpenSSL for RSA verification. On macOS, add `crypto` and the `Security` framework to your linker flags. In CMake:

```
target_link_libraries(YourPlugin PRIVATE
    crypto
    "-framework Security")
```

Step 5 · Connect your store

PrimeLock issues a license automatically the moment a sale is confirmed. You just point your store's webhook at PrimeLock.

Selar

In your Selar product settings, open **Webhook** and paste your Selar Webhook URL (copied from the product page). It looks like this:

```
https://api.primelock.theprimis.org/webhooks/selar
?api_key=YOUR_API_KEY&product=YOUR_SLUG
```

Flutterwave

In Flutterwave → Settings → Webhooks, paste your Flutterwave Webhook URL, and add your webhook hash as the FLW_WEBHOOK_HASH environment variable on your server.

Any other platform

Using Gumroad, Paystack, Stripe, or something else? Use the generic webhook. Configure your platform to POST a JSON body containing at least the customer email:

```
{
  "customer_email": "buyer@example.com",
  "customer_name": "Jane Doe",    // optional
  "order_id":      "ORDER-123"   // optional, dedup
}
```

PrimeLock generates the key and emails it to the customer — no matter which platform triggered the sale.

How it runs, end to end

Once set up, the entire flow is automatic. Here's what happens on every sale:

1	Customer buys	A sale is confirmed on Selar (or your chosen platform).
2	Webhook fires	Your store POSTs the order to PrimeLock.
3	Key generated	PrimeLock creates a unique key, e.g. PL-XKQZ-7YMN-BPFW-2941.
4	Email sent	The key is emailed to the customer instantly from your domain.
5	Customer activates	They open the License Manager, sign in with their email, and click Activate.
6	Token signed	PrimeLock returns an RSA-signed token; the app stores it in the keychain.
7	Plugin unlocks	Your plugin verifies the signature locally at startup — no internet needed again.

The RSA private key lives only on PrimeLock's servers and signs the token once, at activation. Everything after that is verified locally with the public key embedded in your plugin — fast, offline, and tamper-proof.

Pricing models

PrimeLock supports every common model. Set the license type when you issue a key, or let your webhook do it automatically.

Perpetual

Pay once, own forever. The token never expires. Best for one-time purchases.

Subscription

The license carries an expiry date. On each renewal payment, your webhook calls the extend endpoint to push the expiry forward:

```
POST /licenses/:id/extend
Authorization: Bearer YOUR_JWT

{ "days": 30 }
```

Subscribe-to-own

The customer pays monthly until they've paid the full price, then keeps it forever. Extend each month as above; when the threshold is reached, upgrade the license to perpetual:

```
POST /licenses/:id/extend
Authorization: Bearer YOUR_JWT

{ "upgrade_to_perpetual": true }
```

PrimeLock emails the customer automatically on both actions — a renewal confirmation, or a "you own it now" upgrade notice.

Trial

Issue a trial license with an expiry date. Expired trials are blocked automatically, and the SDK surfaces an "ending soon" warning in the final days so you can prompt the customer to buy.

API reference

You rarely call these directly — the SDK and webhooks handle most of it — but here are the core endpoints.

Base URL: <https://api.primelock.theprimis.org>

Method	Endpoint	Purpose	Auth
POST	/licenses	Issue a license manually	Dev JWT
POST	/licenses/activate	Activate on a machine	None
POST	/licenses/validate	Background re-check	None
POST	/licenses/deactivate	Free a seat	None
POST	/licenses/:id/extend	Renew or upgrade	Dev JWT
POST	/licenses/:id/revoke	Revoke a license	Dev JWT
GET	/licenses/:id/activations	Machine history	Dev JWT
POST	/webhooks/selar	Auto-issue on sale	API key
POST	/webhooks/generic	Any platform	API key
POST	/licenses/offline/response	Offline activation	None

Need a hand?

Email support@theprimis.org and a human will help you integrate. Your dashboard always shows your API key, product IDs, webhook URLs, and every license you've issued.

PrimeLock · Powered by PRIMIS · primelock.theprimis.org