

Verificare formula folosind NuSMV (mai nou se numeste NuXMV)

1. Se descarca de aici: [Getting NuSMV \(fbk.eu\)](http://fbk.eu/GettingNuSMV)
2. Tutorial scurt: [tutorial.pdf \(fbk.eu\)](http://fbk.eu/tutorial.pdf)
3. Exemplele pot fi verificate astfel:
 - Se copiaza in folder-ul **bin**
 - Din interiorul folder-ului se deschide **Windows PowerShell**.



- Se tasteaza apoi **./nuxmv** si numele fisierului cu extensie cu tot si se apasa tasta **Enter**

```
Administrator: Windows PowerShell
PS C:\nuXmv-1.1.1-win32\bin> ./nuxmv vehicul.smv
```

- Rezultatul verificarii:

```
Administrator: Windows PowerShell
*** This version of nuXmv is linked to MathSAT
*** Copyright (C) 2009-2016 by Fondazione Bruno Kessler
*** Copyright (C) 2009-2016 by University of Trento
*** See http://mathsat.fbk.eu

-- specification AG ((state = left_up & command = go_down) -> AX state = left_down) is true
-- specification AG ((state = left_up & command = go_right) -> AX state = right_up) is true
-- specification AG ((state = left_up & ((command = go_up | command = go_left) | command = do_nothing)) -> AX state = left_up) is true
-- specification AG ((state = left_down & command = go_up) -> AX state = left_up) is true
-- specification AG ((state = left_down & command = go_right) -> AX state = right_down) is true
-- specification AG ((state = left_down & ((command = go_down | command = go_left) | command = do_nothing)) -> AX state = left_down) is true
-- specification AG ((state = right_up & command = go_down) -> AX state = right_down) is true
-- specification AG ((state = right_up & command = go_left) -> AX state = left_up) is true
-- specification AG ((state = right_up & ((command = go_up | command = go_right) | command = do_nothing)) -> AX state = right_up) is true
-- specification AG ((state = right_down & command = go_up) -> AX state = right_up) is true
-- specification AG ((state = right_down & command = go_left) -> AX state = left_down) is true
-- specification AG ((state = right_down & ((command = go_down | command = go_right) | command = do_nothing)) -> AX state = right_down) is true
-- specification AG (state = right_down -> AX state = left_up) is false
-- as demonstrated by the following execution sequence
Trace Description: CTL Counterexample
Trace Type: Counterexample
-> State: 1.1 <-
  command = go_up
  state = left_up
-> State: 1.2 <-
  command = go_down
-> State: 1.3 <-
  command = go_right
  state = left_down
-> State: 1.4 <-
  command = go_up
  state = right_down
-> State: 1.5 <-
  state = right_up
PS C:\nuXmv-1.1.1-win32\bin>
```