Q

Developer

Login

Access Linux filesystems in Windows and WSL 2



September 10th, 2020



Starting with Windows Insiders preview build 20211, WSL 2 will be offering a new feature: wsl --mount. This new parameter allows a physical disk to be attached and mounted inside WSL 2, which enables you to access filesystems that aren't natively supported by Windows (such as ext4).

So, if you're dual booting with Windows & Linux using different disks, you can now access your Linux files from Windows!

Getting started

To mount a disk, open a PowerShell window with administrator privileges and run:

```
wsl --mount <DiskPath>
```

To list the available disks in Windows, run:

```
wmic diskdrive list brief
```

To unmount and detach the disk from WSL 2, run


```
wsl --unmount <Diskpath>
```

The disks paths are available under the 'DeviceID' columns. Usually under the \\.\\.\PHYSICALDRIVE* format. Below is an example of mounting a specific partition of a given hard disk into WSL and browsing its files.

```
caloewen@DESKTOP-SNUDIE2:
                                                                                        PS C:\Users\Craig> wmic diskdrive list brief
                                            Model
                                                                    Partitions Size
Microsoft Virtual Disk \\.\PHYSICALDRIVE3 Microsoft Virtual Disk
                                                                                 136358691840
Virtual HD ATA Device
                        \\.\PHYSICALDRIVE1 Virtual HD ATA Device
                                                                                 32210196480
                       \\.\PHYSICALDRIVE0 Virtual HD ATA Device
                                                                                 42944186880
Virtual HD ATA Device
Microsoft Virtual Disk \\.\PHYSICALDRIVE2 Microsoft Virtual Disk 3
                                                                                 42944186880
PS C:\Users\Craig> wsl --mount \\.\PHYSICALDRIVE2 --partition 1
The disk \\.\PHYSICALDRIVE2 was successfully mounted under the name 'PHYSICALDRIVE2p1'. The
mountpoint can be found under the path pointed to by the automount setting (default: /mnt/ws
To unmount and detach the disk, run 'wsl --unmount \\.\PHYSICALDRIVE2'.
PS C:\Users\Craig> wsl
To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.
caloewen@DESKTOP-SNUDIE2:/mnt/c/Users/Craig$ cd /mnt/wsl/PHYSICALDRIVE2p1/
caloewen@DESKTOP-SNUDIE2:/mnt/wsl/PHYSICALDRIVE2p1$ ls
                  initrd.img.old lost+found opt run srv
lib media proc sbin sys
dev initrd.img lib64
                                                          tmp
                                                               vmlinuz
caloewen@DESKTOP-SNUDIE2:/mnt/wsl/PHYSICALDRIVE2p1$
```

Accessing these files with File Explorer

Once mounted, it's also possible to access these disks through the Windows explorer by navigating to \wsl\$ and then to the mount folder.



Limitations

By default, wsl --mount attempts to mount the disk as ext4. To specify a filesystem, or for more advanced scenarios, check out Mount a disk in WSL 2.

Also please note that this feature comes with the limitation that only physical disks can be attached to WSL 2. At this time, it's not possible to attach a single partition. More details on the limitations here.

Give us your feedback!

If you run into any issues, or have feedback for our team please file an issue on our Github, and if you have general questions about WSL you can find all of our team members that are on Twitter on this twitter list.



Pierre Boulay

Software Engineer II, Linux on Windows

Follow 5

Posted in Command Line

Read next

Windows Package Manager Preview (v0.2.2521)

We have been humbled by all the positive support for the Windows Package Manager. You have taken us from zero to over one thousand packages in six months. This is an ...



Demitrius Nelon September 22, 2020

7 comments

Windows Terminal Preview 1.4 Release

Welcome to another release of Windows Terminal Preview and Windows Terminal! Windows Terminal Preview is now on version 1.4 and will have the new features listed below. ...



Kayla Cinnamon September 22, 2020

13 comments


42 comments

Comments are closed. Login to edit/delete your existing comments



2







Ascii Wolf September 11, 2020 2:32 am Cool! Now, if only SFTP support was added to Explorer as well, I would be happy. $\stackrel{\square}{\cup}$ Pierre Boulay September 14, 2020 11:58 am \vee © You can mount an SFTP share in WSL, and then access it through the \WSL\$ path in the Windows Explorer. Ryan Avery October 2, 2020 4:43 pm \vee ©

Pierre, does this actually work? I just tried mounting an SSHFS system in WSL2. It mounts fine and files are available in Ubuntu, but when I use Explorer and browse to the mounted folder, I get the error message:

"\wsl\$\Ubuntu\mnt\test_mount is not accessible. You might not have permission to use this network resource. Contact the administrator of this server to find out if you have access permissions.

Attempt to access invalid address."

If it helps, I am using the following to mount:

```
sshfs -o idmap=user server:/files /mnt/test_mount
```

And server is aliased in my .ssh/config to the hostname, port, and username for that server

Note that when unmounted, windows explorer can open the folder, but of course the contents are empty.

Thanks!



Pierre Boulay October 12, 2020 3:54 pm



This is probably caused by a uid mismatch.

To make the mountpoint accessible in the explorer, the uid needs to match the default wsl user for your distro.

To figure out your uid, run id -u inside WSL.

Once you have that, change your mount command line to something like:

sshfs -o idmap=user server:/files /mnt/test_mount uid=[uid here (without the brackets)]

If that doesn't work, I recommend <u>creating an issue</u>

Jason Jarvis

September 11, 2020 7:54 am



How's the performance?



Pierre Boulay ==

September 14, 2020 11:58 am



✓ ⊗

Should be close to native from inside WSL 2. From the Windows Explorer there is some penalty

Stefan Maric September 11, 2020 8:14 am



If the whole device is exposed to the Linux kernel, does that mean I could mount an encrypted LUKS volume inside WSL and navigate the fs using explorer.exe?

That would be awesome. It would mean one doesn't need VeraCrypt for disk encryption interop between windows and linux.





Pierre Boulay September 14, 2020 12:01 pm



You can as long as the Linux kernel supports dm-crypt.

Unfortunately the kernel that we currently ship doesn't, but you can build you own (just make sure that CONFIG_DM_CRYPT is 'y'), and then install in %windir%\system32\lxss\tools\kernel





 $https://devblogs.microsoft.com/commandline/access-linux-filesystems-in-windows-and-wsl-2/?ranMID=46131\&ranEAID=a1LgFw09t88\&ranSiteID=a1LgFw09t88-GnlFebPGb8FuvVs8xTlSrQ\&epi=a1LgFw09t88-GnlFebPG. \\ 5/8$

September 12, 2020 8:39 am

K Kaland

Does the limitation of only working with disks mean it's not possible to mount Linux partitions if they are on the same physical disk (boot disk) as Windows, e.g. on a laptop?



Pierre Boulay #

September 14, 2020 12:13 pm



Yes, this scenario isn't supported at this time.





Does this make it possible to use a physical disk for a WSL root filesystem? It would be truly amazing if one could have a full-fledged dual-boot setup that could also double as WSL.



Pierre Boulay

September 14, 2020 12:15 pm



That's an interesting idea.

It's not possible to boot directly on a mounted disk, but you can chroot into it after mounting it.



Ihor Dutchak October 19, 2020 6:26 am



but you can chroot into it after mounting it

Would be cool to have a way to chroot to a specific device quickly, like wsl -chroot \.\PHYSICALDRIVE... without need to mount a drive -> mount all the /dev/... /proc/... etc. -> chroot...



Pierre Boulay

October 19, 2020 12:42 pm



 \vee ©

That's an interesting idea.

I'd recommend <u>creating a feature request</u>

tsuki Shimo September 15, 2020 12:32 am



 \vee ©

Can WSL2 mount other filesystem like JFS with this function?



September 24, 2020 3:31 pm



The kernel that we officially ship doesn't support JFS at this time, but if you build your own, you should be able to mount a JFS volume.

Rohat Bozyil September 20, 2020 10:37 pm



Hello Pierre

Is this functionality only limited to storage devices, or would it enable me to make use of peripheral devices which connect through the same USB receptacles?


An example would be if I could use a wired joystick-controller that makes use of the USB type-A interface, the same way I use USB type-A for my flash drive.




This feature is only limited to storage devices. Unfortunately it can't be used to pass-through a USB device to WSL 2.

✓ ⊗







Archive

August 2021

July 2021

May 2021

April 2021

March 2021

January 2021

December 2020

November 2020

October 2020

September 2020

August 2020

Stay informed



What's new	Microsoft Store	Education	Enterprise		Developer	Company
Surface Pro 8	Account profile	Microsoft in education	Azure		Microsoft Visual Studio	Careers
Surface Laptop Studio	Download Center	Office for students	AppSource		Windows Dev Center	About Microsoft
Surface Pro X	Microsoft Store support	Office 365 for schools	Automotive		Developer Center	Company news
Surface Go 3	Returns	Deals for students &	Government		Microsoft developer	Privacy at Microsoft
Surface Duo 2	Order tracking	parents	Healthcare		program	Investors
Surface Pro 7+	Virtual workshops and	Microsoft Azure in education	Manufacturing		Channel 9 Microsoft 365 Dev Center	Diversity and inclusion
Windows 10 apps	training		Financial services			Accessibility
HoloLens 2	Microsoft Store Promise		Retail		Microsoft 365 Developer Program	Security
	Flexible Payments				Microsoft Garage	
English (United States)	Sitemap	Contact Microsoft Privacy	Terms of use	Trademarks	Safety & eco About ou	r ads © Microsoft 2021