

To install OpenVPN Access Server in AWS using Docker and activate the license key, you can follow these steps:

Install Openvpn Access Server

- Launch an EC2 instance in AWS:
 - Sign in to your AWS Management Console.
 - Go to the EC2 service.
 - Click on "Launch Instance" to create a new instance.
 - Choose an appropriate Amazon Machine Image (AMI) for your instance. You can
 use a Linux-based AMI like Amazon Linux or Ubuntu Server.
 - Select an instance type that suits your requirements.
 - Configure the instance details as per your needs.
 - Add storage, tags, and security group settings.
 - Review the instance details and launch the instance.
- Connect to your EC2 instance:
 - Once the instance is running, you need to connect to it via SSH.
 - Use a terminal or SSH client to connect to the instance using the key pair you selected during the instance launch.
- Install Docker:
 - Update the package repository: sudo apt update
 - Install Docker and other necessary packages: sudo apt install docker.io
- Pull the OpenVPN Access Server Docker image:
 - Run the following command to pull the OpenVPN Access Server image: sudo docker pull linuxserver/openvpn-as
- Start the OpenVPN Access Server container:
 - Execute the following command to start the container, replacing YOUR HOSTNAME with your desired hostname:

docker create --name=openvpn-as --restart=always -v /home/ecs-user/docker/openvpn-as/config:/config -e INTERFACE=eth0 -e PGID=1001 -e PUID=1001 -e TZ=Asia/Singapore -p 943:943 -p 1194:1194/udp -p 9443:9443 -- privileged linuxserver/openvpn-as



• Wait for a few moments to allow the container to start, then start the vpn service

sudo docker start openvpn-as


Set username and password

docker exec -it openvpn-as passwd admin

OpenVPN Access Server Subscriptions

Make sure that you're running at least version 2.8.1 of Access Server. Then, follow these steps to purchase and activate a subscription:

1. Login (or create an account) to openvpn.net and click on subscriptions.






Choose the number of VPN connections to purchase, select your automatic renewal of monthly or yearly, then click on **Purchase**.

Choose a plan and the number of connections you need. Cost per connection decreases as your number of connections increases. Choose key type— Specify key details How many simultaneous connections do you need? - 5 + Free 5 10 25 50 100 250 500 2000 More Billed Monthly \$14.00 per connection /mo

Total for Subscription per month: 70.00 Proceed To Payment Back



 Go through the purchase and checkout process to pay for the subscription, then click on Copy Key from your subscription details.



Activate the OpenVPN License Key


 Go to your Admin Web UI in a web browser. (It is accessible at the IP address or DNS address of your server. For example, if your server's IP address is

https://<EC2 instance public IP/FQDN>:9443/admin




Login as an administrative user (the default user is openvpn).






• Once logged in, click on **Configuration > Activation**.



Paste your key into the 'Enter Activation here' field and click on Activate. Wait
momentarily for the subscription to load. You should then receive the message,
"Subscription is active and operating normally".





Activation Manager Get Activation Key Activated Keys VPN Connections Subscription 1 (10) 1/10 Deactivate Subscription is active and operating normally