

Password Reset Guide

Acme Cloud Platform - Support Documentation

Last Updated: January 2025

1. Self-Service Password Reset

If you have forgotten your password, you can reset it yourself by following these steps:

Step 1: Navigate to the login page at <https://dashboard.acmecloud.io/login>

Step 2: Click the "Forgot Password?" link below the password field.

Step 3: Enter the email address associated with your Acme Cloud account.

Step 4: Click "Send Reset Link" to receive a password reset email.

Step 5: Check your inbox for an email from no-reply@acmecloud.io (check Spam/Junk folders if you do not see it within 5 minutes).

Step 6: Click the reset link in the email. The link is valid for 1 hour.

Step 7: Enter your new password. It must meet the following requirements:

- Minimum 12 characters in length
- At least one uppercase letter (A-Z)
- At least one lowercase letter (a-z)
- At least one number (0-9)
- At least one special character (!@#\$%^&*)
- Cannot be any of your last 5 passwords

Step 8: Confirm your new password by typing it again.

Step 9: Click "Reset Password" to save your new credentials.

You will be automatically logged in after a successful password reset. All other active sessions will be terminated for security.

2. Admin-Initiated Password Reset

Organization administrators can reset passwords for team members:

Step 1: Log into the Acme Cloud Dashboard with admin credentials.

Step 2: Navigate to Organization > Team Members.

Step 3: Find the user whose password needs to be reset.

Step 4: Click the three-dot menu next to their name and select "Reset Password".

Step 5: Choose either:

- a) Send reset email - Sends a password reset link to the user's email.
- b) Set temporary password - Generates a temporary password that the user must change on next login.

Step 6: Notify the user through a secure channel (not email) if using option (b).

Note: Admin password resets are logged in the audit trail for security compliance.

3. CLI Password Reset

For users who prefer the command line:

```
acme auth reset-password --email your@email.com
```

This command triggers the same password reset flow as the web interface. A reset link will be sent to the specified email address.

To change your password while logged in:

```
acme auth change-password --current "old_password" --new "new_password"
```

Note: Passwords must meet the same complexity requirements as the web interface.

4. Troubleshooting Password Reset Issues

Problem: Reset email not received

Solution:

- Check your Spam/Junk folder
- Verify you are using the correct email address
- Whitelist no-reply@acmecloud.io in your email provider
- Wait up to 10 minutes (email delays can occur during peak hours)
- Try requesting a new reset link after 15 minutes

Problem: Reset link expired

Solution:

- Reset links are valid for 1 hour only
- Request a new reset link from the login page
- Do not bookmark reset links as they are single-use

Problem: New password not accepted

Solution:

- Ensure the password meets all complexity requirements
- The new password cannot match any of your last 5 passwords
- Avoid using common passwords or dictionary words
- Try a passphrase like "Correct-Horse-Battery-Staple-42!"

Problem: Still locked out after reset

Solution:

- Clear your browser cache and cookies
- Try logging in from an incognito/private window
- If 2FA is enabled, ensure your authenticator app is synced
- Contact support@acmecloud.io for further assistance

5. Security Recommendations

To keep your account secure:

1. Use a unique password that you do not use on any other website.
2. Enable Two-Factor Authentication (2FA) in Dashboard > Settings > Security.
3. Use a password manager (e.g., 1Password, Bitwarden, LastPass) to generate and store strong passwords.
4. Change your password every 90 days (required for Enterprise accounts).
5. Never share your password via email, chat, or phone.
6. Review your active sessions regularly: Dashboard > Settings > Sessions.
7. Enable login notifications: Dashboard > Settings > Security > Email alerts.

For additional security assistance, contact: security@acmecloud.io