Exploit Telnet con Metasploit

Obiettivo:

utilizzare Metasploit per sfruttare la vulnerabilità relativa a Telnet con il modulo auxiliary telnet_version sulla macchina Metasploitable.

Configurazione:

Ip kali linux: 192.168.1.25

```
4: eth2: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP group default qlen 1000 link/ether 08:00:27:6d:32:14 brd ff:ff:ff:ff:ff
inet 192.168.1.25/24 brd 192.168.1.255 scope global noprefixroute eth2
valid_lft forever preferred_lft forever
inet6 fe80::8485:586b:a75c:2c0a/64 scope link noprefixroute
valid_lft forever preferred_lft forever
```

Ip metasploitable: 192.168.1.40

```
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast qlen 1000
link/ether 08:00:27:8f:37:6d brd ff:ff:ff:ff:ff
inet 192.168.1.40/24 scope global eth0
```

Rilevamento versione di telnet

Ricerca del modulo adatto

Controllo e configurazione delle opzioni

Lancio del payload con il comando exploit e ottenimento delle credenziali d'accesso a Telnet

Accesso

```
) > telnet 192.168.1.40
msf6 auxiliary(
[*] exec: telnet 192.168.1.40
Trying 192.168.1.40 ...
Connected to 192.168.1.40.
Escape character is '^]'.
Warning: Never expose this VM to an untrusted network!
Contact: msfdev[at]metasploit.com
Login with msfadmin/msfadmin to get started
metasploitable login: msfadmin
Password:
Last login: Tue May 13 10:37:17 EDT 2025 from 192.168.1.25 on pts/1
Linux metasploitable 2.6.24-16-server #1 SMP Thu Apr 10 13:58:00 UTC 2008 1686
The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.
To access official Ubuntu documentation, please visit:
http://help.ubuntu.com/
No mail.
msfadmin@metasploitable:~$ ls
vulnerable
msfadmin@metasploitable:~$
```