

Sierra Wireless FW

```
1 Option1:
2 ./fwdwl-litehostx86_64 -d /dev/ttyUSB3 --fwpath "./swi_fw0105/" \
3   -e1 --logfile "fwdwl-lite-test.log"
4
5 Option2:
6 ./fwdwl-litehostx86_64 -d /dev/ttyUSB3 --fwpath "./swi_fw0105/" \
7   -e1 -p /dev/cdc-wdm0 -c MBIM --logfile "fwdwl-lite-test.log"
8
9
```



SLQS04.00.27-....tar.xz
01 Apr 2022, 12:26 AM

SLQS04.00.27-lite.bin	8 elementos	Carpeta
tools	1 elemento	Carpeta
SampleApps	4 elementos	Carpeta
lite-qmi-demo	10 elementos	Carpeta
lite-fw-download	5 elementos	Carpeta
bin	10 elementos	Carpeta
swi_fw0105	2 elementos	Carpeta
fwdwl-lite-test.log	18,1 kB	Texto
fwdwl-lite-cdc-wdm2.log	4,9 kB	Texto
fwdwl-litearmhf	2,1 MB	Programa
fwdwl-litearm64le	2,7 MB	Programa
fwdwl-liteppc	2,7 MB	Programa
fwdwl-litearm64	2,4 MB	Programa
fwdwl-litearm	2,6 MB	Programa
fwdwl-litehosti686	2,7 MB	Programa
fwdwl-litehostx86_64	3,0 MB	Programa
src	3 elementos	Carpeta
inc	1 elemento	Carpeta
readme	2,7 kB	Texto
makefile	825 bytes	Texto
lite-connection-manager	5 elementos	Carpeta
SampleApps.mak	1,6 kB	Texto
pkgs	1 elemento	Carpeta
docs	2 elementos	Carpeta
lite-qmux	2 elementos	Carpeta
lib	9 elementos	Carpeta
inc	8 elementos	Carpeta
lite-qmi	2 elementos	Carpeta
lib	9 elementos	Carpeta
armhf	1 elemento	Carpeta
arm64le	1 elemento	Carpeta

Error 100:

```
1 eFW_TYPE_CWE_NVU
2 Tx(48):02 00 00 00 30 00 00 00 02 00 00 00 02 00 00 00 .. 00 00 00
3 litefw_DownloadFW failed: 100
4 Exiting Application!!!
```

Try:

```
1 | ./fwdwl-litehostx86_64 -c MBIM -d /dev/ttyUSB3 -p /dev/$devpath --fwpath "./swi_fw0105/" -e1  
--logfile "fwdwl-lite-test.log"
```

Low power mode:

```
1 | AT!GSTATUS?  
2 | !GSTATUS:  
3 | Current Time: 87 Temperature: 40  
4 | Reset Counter: 1 Mode: LOW POWER MODE
```

Try:

```
1 | ./fwdwl-litehostx86_64 -c MBIM -d /dev/ttyUSB3 -p /dev/cdc-wdm0 --fwpath "./swi_fw0105/" -e1  
--logfile "fwdwl-lite-test.log"
```