

Setting up Access Control

with Roles

zpl.in/contracts-workshop

Francisco Giordano

frangio@openzeppelin.com

@frangio_

OpenZeppelin

Our mission is to protect the open economy

OpenZeppelin is a software company that provides **security audits** and **products** for decentralized systems.

Projects from any size — from new startups to established organizations — trust OpenZeppelin to build, inspect and connect to the open economy.































Security, Reliability and Risk Management

OpenZeppelin provides a complete suite of **security and reliability products** to build, manage, and inspect all aspects of software development and operations for Ethereum projects.



OpenZeppelin Contracts

Token Standards

ERC20, ERC721, ...

Security modules

Reentrancy guard, pull payments

Governance

Timelock, & more coming...

+ Extensions

Pausable, snapshots, ...

Utilities

Cryptography, math, create2, data structures, ...

Proxies

Upgradeability, clones

→ **Upgrades Plugins**

Automated upgradeability with security checks

Access Control

Ownable & Roles


Ownable

Simple access control: Ownable

```
NFT
- ownerOf( )
- transfer( )
- mint( )
```




Simple access control: Ownable



Ownable Interface

```
contract Ownable {
    function owner() view returns (address);
    function transferOwnership(address newOwner) onlyOwner;
    function renounceOwnership() onlyOwner;
}
```

Simple access control: Ownable



Analysing Risks


Assess impact of compromised keys


Design key storage system

Plan mitigation measures

Different considerations can apply within a single contract

Granular access control








Responder

StablestCoin

- balanceOf()
- transfer()
- setFee()
- emergencyShutdown()





Responder

AccessControl

@openzeppelin/contracts/access/AccessControl.sol

AccessControl

```
import "@openzeppelin/contracts/access/AccessControl.sol";
contract StablestCoin is ERC20, AccessControl {
   ...
```

AccessControl Interface

```
contract AccessControl {
    function hasRole(bytes32 role, address account) view returns (bool);
    function _setupRole(bytes32 role, address account) internal;
    function grantRole(bytes32 role, address account) onlyAdmin(role);
    function revokeRole(bytes32 role, address account) onlyAdmin(role);
    function getRoleAdmin(bytes32 role) view returns (bytes32);
    function renounceRole(bytes32 role, address account);
bytes32 constant MINTER_ROLE = keccak256("MINTER_ROLE");
require(hasRole(MINTER_ROLE, msg.sender));
_setupRole(MINTER_ROLE, msg.sender);
```

Granting & Revoking Roles




Fee Setter

Responder

StablestCoin


- balanceOf()
- transfer()
- setFee()
- emergencyShutdown()






Responder

Admins






Admins

Every role has an admin role

```
contract AccessControl {
   function hasRole(bytes32 role, address account) view returns (bool);
   function _setupRole(bytes32 role, address account) internal;
   function grantRole(bytes32 role, address account) onlyAdmin(role);
   function revokeRole(bytes32 role, address account) onlyAdmin(role);
   function getRoleAdmin(bytes32 role) view returns (bytes32);
   function renounceRole(bytes32 role, address account);
}
```


Default Admin

Every role initially has a global default admin role





Renouncing

```
contract AccessControl {
   function hasRole(bytes32 role, address account) view returns (bool);
   function _setupRole(bytes32 role, address account) internal;
   function grantRole(bytes32 role, address account) onlyAdmin(role);
   function revokeRole(bytes32 role, address account) onlyAdmin(role);
   function getRoleAdmin(bytes32 role) view returns (bytes32);
   function renounceRole(bytes32 role, address account);
}
```









```
contract TimelockController is AccessControl {
    bytes32 public constant TIMELOCK_ADMIN_ROLE = keccak256("TIMELOCK_ADMIN_ROLE");
    bytes32 public constant PROPOSER_ROLE = keccak256("PROPOSER_ROLE");
    bytes32 public constant EXECUTOR_ROLE = keccak256("EXECUTOR_ROLE");
    constructor(uint256 minDelay) {
        _setRoleAdmin(TIMELOCK_ADMIN_ROLE, TIMELOCK_ADMIN_ROLE);
        _setRoleAdmin(PROPOSER_ROLE, TIMELOCK_ADMIN_ROLE);
        _setRoleAdmin(EXECUTOR_ROLE, TIMELOCK_ADMIN_ROLE);
        _setupRole(TIMELOCK_ADMIN_ROLE, _msgSender());
        _setupRole(TIMELOCK_ADMIN_ROLE, address(this));
```



https://zpl.in/wizard

What's next? Focus on UX

onlyRole modifier


Revert reasons hinting at missing role

Subgraph

https://zpl.in/subgraph/access-control

Defender support

https://defender.openzeppelin.com



@openzeppelin/contracts docs.openzeppelin.com forum.openzeppelin.com defender.openzeppelin.com

Thank you!

Learn more

openzeppelin.com/contracts forum.openzeppelin.com docs.openzeppelin.com

Contact

@frangio_
frangio@openzeppelin.com