

//program to return no. of character in the string from server side to the client side

// server side program:-

```
import java.net.*;
import java.io.*;
class ser
{
    public static void main(String[]args) throws Exception{
        System.out.println("server Started");
        ServerSocket S1 = new ServerSocket(1234);
        while(true)
        {
            Socket l1 = S1.accept();

            BufferedReader cli = new BufferedReader(new InputStreamReader(l1.getInputStream()));
            BufferedReader ser = new BufferedReader(new InputStreamReader(System.in));
            DataOutputStream clio = new DataOutputStream(l1.getOutputStream());
            String str1,str2;
            str1 = cli.readLine();
            System.out.println(str1);
            int l = str1.length();
            str2 = ser.readLine();
            clio.writeBytes(l+"\n");

        }
    }
}
```

// Client side program:-

```
import java.net.*;
import java.io.*;
class cli
{
    public static void main(String[]args) throws Exception{
        while(true)
        {
            System.out.println("enter string");
            Socket s1 = new Socket("localhost",1234);
            BufferedReader b1 = new BufferedReader(new InputStreamReader(System.in));
            BufferedReader b2 = new BufferedReader(new InputStreamReader(s1.getInputStream()));
            DataOutputStream d1 = new DataOutputStream(s1.getOutputStream());
            String str1,str2;
            str1 = b1.readLine();
            d1.writeBytes(str1+"\n");
            str2 = b2.readLine();
            System.out.println(str2);
            System.out.println();
            s1.close();
        }
    }
}
```

```
}
```

//output:-

//cli:- client side

//ser:- Server side

```
PS C:\Users\moham\Desktop\ADA_PRAC_VIVS\AP_pogram\client_server_prac1> javac cli.java
PS C:\Users\moham\Desktop\ADA_PRAC_VIVS\AP_pogram\client_server_prac1> javac cli.java
PS C:\Users\moham\Desktop\ADA_PRAC_VIVS\AP_pogram\client_server_prac1> java cli
enter string
hello
5
enter string
```

```
PS C:\Users\moham\Desktop\ADA_PRAC_VIVS\AP_pogram\client_server_prac1> java ser.java
PS C:\Users\moham\Desktop\ADA_PRAC_VIVS\AP_pogram\client_server_prac1> java ser.java
server Started
hello
```

```
□
```