OracleDaemonConfig

- Source code
- Deployed contract

OracleDaemonConfig acts as a parameters registry for the Lido oracle daemon. The full list of params are provided in the Lido V2 mainnet parametersguide.

note In contrast to Oracle Report Sanity Checker, the stored values aren't enforced by the protocol on-chain code.

View methods

get(string calldata _key)

Retrieves the value corresponding to the provided key.

function
get (string
calldata _key)
external
view
returns
(bytes

getList(string[] calldata _keys)

memory) note Reverts if value is missing.

Retrieves a list of values corresponding to the provided keys.

function

getList (string []

calldata keys)

external

view

returns

(bytes[]

memory) note Reverts if any value for a specific key is missing.

Methods

set(string calldata _key, bytes calldata _value)

Sets the value for the provided key. Can only be called by users with CONFIG_MANAGER_ROLE .

function

set (string

calldata_key,

bytes

calldata_value)

external note Reverts if any of the following is true:

- · value with provided key already exists
- value is empty
- · called by someone who doesn't have CONFIG_MANAGER_ROLE
- role

update(string calldata _key, bytes calldata _value)

Updates the value for the provided key. Can only be called by users with CONFIG_MANAGER_ROLE .

function

update (string

calldata _key,

bytes

calldata_value)

external note Reverts if any of the following is true:

- · value with provided key doesn't exist
- · value is the same with the one already set
- · value is empty
- called by someone who doesn't haveCONFIG_MANAGER_ROLE
- role

unset(string calldata _key)

Removes the value of the provided key. Can only be called by users with CONFIG_MANAGER_ROLE.

function

unset (string

calldata _key)

external note Reverts if any of the following is true:

- · value with provided key doesn't exist
- called by someone who doesn't haveCONFIG_MANAGER_ROLE
- role

Events

ConfigValueSet

Emitted when a new key-value pair is set.

event

ConfigValueSet (string

indexed key,

bytes value)

ConfigValueUpdated

Emitted when a key-value pair is updated.

event

ConfigValueUpdated (string

indexed key,

bytes value)

ConfigValueUnset

Emitted when a key-value pair is unset.

event

ConfigValueUnset (string

indexed key) Edit this page Previous OracleReportSanityChecker Next StakingRouter