## seid tx gov submit-proposal execute-contract

Submit a execute wasm contract proposal (run by any address)

Usage: seid tx gov submit-proposal execute-contract [contract addr bech32] [json encoded migration args] [flags]

Flags: -a, --account-number uint The account number of the signing account (offline mode only) --amount string Coins to send to the contract during instantiation -b, --broadcast-mode string Transaction broadcasting mode (sync|async|block) (default "sync") --deposit string Deposit of proposal --description string Description of proposal --dry-run ignore the --gas flag and perform a simulation of a transaction, but don't broadcast it (when enabled, the local Keybase is not accessible) --feeaccount string Fee account pays fees for the transaction instead of deducting from the signer --fees string Fees to pay along with transaction; eg: 10uatom --from string Name or address of private key with which to sign --gas string gas limit to set per-transaction; set to "auto" to calculate sufficient gas automatically (default 200000) --gas-adjustment float adjustment factor to be multiplied against the estimate returned by the tx simulation; if the gas limit is set manually this flag is ignored (default 1) --gas-prices string Gas prices in decimal format to determine the transaction fee (e.g. 0.1uatom) --generate-only Build an unsigned transaction and write it to STDOUT (when enabled, the local Keybase only accessed when providing a key name) -h, --help help for execute-contract --keyring-backend string Select keyring's backend (os|file|kwallet|pass|test|memory) (default "os") --keyring-dir string The client Keyring directory; if omitted, the default 'home' directory will be used --ledger Use a connected Ledger device --node string; to tendermint rpc interface for this chain (default "tcp://localhost:26657") --note string Note to add a description to the transaction (previously --memo) --offline Offline mode (does not allow any online functionality -o, --output string Output format (text|json) (default "json") --proposal string Proposal file path (if this path is given, other proposal flags are ignored) --run-as string The address that is passed as sender to the contract on proposal execution -s, --sequence uint The sequence number of the signing account (offline mode only) sign-mode string Choose sign mode (direct|amino-json), this is an advanced feature --timeout-height uint Set a block timeout height to prevent the tx from being committed past a certain height --title string Title of proposal --type string Permission of proposal, types: store-code/instantiate/migrate/update-admin/clear-admin/text/parameter change/software upgrade -y, -yes Skip tx broadcasting prompt confirmation

Global Flags: --chain-id string The network chain ID --home string directory for config and data (default "~/.sei") --log\_format string The logging format (json|plain) --log\_level string The logging level (trace|debug|info|warn|error|fatal|panic) --trace print out full stack trace on errors Last updated onJuly 1, 2024 <a href="mailto:community-pool-spend">community-pool-spend</a> <a href="mailto:ibc-upgrade">ibc-upgrade</a>