Commands

Usage:namadac utils [OPTIONS]

join-network

Configure Namada to join an existing network. See the networks page for details on how to join a network.

namadac

utils

join-network

--chain-id

< some-chain-i d

fetch-wasms

Ensure pre-built wasms are present.

namadac

utils

fetch-wasms

--chain-id

< chain-i d

validate-wasm

Check that the provided wasm code is valid by the Namada standards.

namadac

utils

validate-wasm

--code-path

< code-pat h

--chain-id

< chain-i d

init-network

Initialize a new test network.

namadac

utils

init-network

--templates-path

< templates-pat h

--wasm-checksums-path

< wasm-checksums-pat h

--chain-prefix

< chain-prefi x

--genesis-time

< genesis-tim e

--chain-id

< chain-i d

derive-genesis-addresses

Derive account addresses from a genesis txs toml file.

namadac

utils

derive-genesis-addresses

--path

< pat h

--chain-id

< chain-i d

genesis-bond

Bond to a validator at pre-genesis.

namadac

utils

genesis-bond

--validator

< validato r

--amount

< amoun t

--path

< pat h

--chain-id

< chain-i d

init-genesis-established-account

Initialize an established account available at genesis.

namadac

utils

init-genesis-established-account

--path

< pat h

--chain-id

< chain-i d

init-genesis-validator

Initialize genesis validator's address, consensus key and validator account key and use it in the ledger's node. Appends validator creation and self-bond txs to a .toml file containing an established account tx.

namadac

utils

init-genesis-validator

--alias

< alia s

--address

< addres s

--path

< pat h

    --net-address

< net-addres s

--commission-rate

< commission-rat e

--max-commission-rate-change

< max-commission-rate-chang e

    --self-bond-amount

< self-bond-amoun t

--email

< emai l

--chain-id

< chain-i d

pk-to-tm

Convert a validator's consensus public key to a Tendermint address.

namadac

utils

pk-to-tm

--public-key

< public-ke y

--chain-id

< chain-i d

default-base-dir

Print the default base directory that would be used if --base-dir or NAMADA_BASE_DIR were not used to set the base directory.

namadac

utils

default-base-dir

epoch-sleep

Query for the current epoch, then sleep until the next epoch.

namadac

utils

epoch-sleep

validate-genesis-templates

Validate genesis templates.

namadac

utils

validate-genesis-templates

--path

< pat h

--chain-id

< chain-i d

test-genesis

Dry run genesis files and get a report on problems that may be found.

namadac

utils

test-genesis

--path

< pat h

--chain-id

< chain-i d

sign-genesis-txs

Sign genesis transaction(s).

namadac

utils

sign-genesis-txs

--path

< pat h

--chain-id

< chain-i d

help

Print this message or the help of the given subcommand(s).

namadac

utils [COMMAND] --help

[Campfire Testnet](#)