File Machine View Input Devices Help

1 2 3 4

10:25

kali@kali: ~

File Actions Edit View Help

```
┌──(kali㉿kali)-[~]
└─$ msfconsole
Metasploit tip: Tired of setting RHOSTS for modules? Try globally setting it
with setg RHOSTS x.x.x.x


[%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%| $a,         |%%%%%%%%%%%%%%%%%%%%%%%%%%%]
[%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%| $S ?a,      |%%%%%%%%%%%%%%%%%%%%%%%%%%%]
[%%%%%%%%%%__%%%%%%%%%%%%%%%%%%%%|    `?a,     |%%%%%%%%__%%%%%%%%__%%__ %%%%]
[% .-——— ..-—.|  _.-—.-.|       ..,a$%|.-——-.| |.-——-.|_|| |_ %%]
[% |       || -_|| _|| _ ||        ,,aS$""` || _ || || _ | |%%]
[% |_____||_____||__||__.__||%$P"`          || __||__||__||__||___||%%]
[%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%|   `"a,     ||__|%%%%%%%%%%%%%%%%%%%%%%%%]
[%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%|     `"a,$$__|%%%%%%%%%%%%%%%%%%%%%%%%%%%%]
[%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%|___      `"$   %%%%%%%%%%%%%%%%%%%%%%%%%%%]
[%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%%]


       =[ metasploit v6.3.43-dev                          ]
+ -- --=[ 2376 exploits - 1232 auxiliary - 416 post       ]
+ -- --=[ 1391 payloads - 46 encoders - 11 nops           ]
+ -- --=[ 9 evasion                                       ]

Metasploit Documentation: https://docs.metasploit.com/

msf6 > use auxiliary/scanner/telnet/telnet_version
msf6 auxiliary(scanner/telnet/telnet_version) > show options

Module options (auxiliary/scanner/telnet/telnet_version):

   Name      Current Setting  Required  Description
   ----      ---------------  --------  -----------
   PASSWORD                   no        The password for the specified username
   RHOSTS                     yes       The target host(s), see https://docs.metasploit.com/docs/using-metasploit/
                                        basics/using-metasploit.html
   RPORT     23               yes       The target port (TCP)
   THREADS   1                yes       The number of concurrent threads (max one per host)
   TIMEOUT   30               yes       Timeout for the Telnet probe
   USERNAME                   no        The username to authenticate as


View the full module info with the info, or info -d command.

msf6 auxiliary(scanner/telnet/telnet_version) > 
```

Right Ctrl