


Portal management

Lenovo internal only

Lenovo


XClarity One user interface



Context menu

The context menu can be found on the right. It will change depending on what page the user is on, but the default menu has the following sections:

- Overview
 - Use this section to manage the organizations and portal users
 - Available to organization administrators or portal user administrators
- Requested organizations
 - Use this section to manage requests sent by customers
 - Available to organization administrators
- Organizations users
 - Use this section to manage all the users from all the organizations
 - Available to portal user administrators




Creating an organization

An organization administrator can create an organization by clicking the + button and then entering the necessary information in the pop-up window.

Notes:

- The organization name should be unique
- The owner email address should belong to the organization's first user, and they will have full access (all roles) – other owners can be added later
- Activate the **Set as a service provider** setting



The screenshot shows the 'Organizations' management interface. A blue '+' button in the top right corner is highlighted with a red square, indicating where to click to create a new organization. A modal window titled 'Create organization' is open in the center. The modal contains the following fields and options:

- Create organization** (Section Header)
- Complete the following fields to create a new organization. Reach out to Lenovo XClarity Support for any assistance. (Instructions)
- Organization name* (Text input field)
- Location* (Dropdown menu)
- Lenovo customer number* (Text input field)
- Owner email address* (Text input field)
- ☐ Set as a service provider ⓘ (Toggle switch)
- Cancel (Button)
- Create organization (Button)

In the background, a table of existing organizations is visible with columns for location and Lenovo Customer Number.

	Lenovo Customer Number
taly	123
entina	1111
entina	123
bania	123

1 - 4 of 4

Organization status

An organization can be in one of five states:

- **Pending:** an organization is in this state from its creation until the first login of the owner
- **Active:** an organization is in this state after the first login of the owner
- **Disabled:** an organization can be put into and taken out of this state – users are not able to access a disabled organization
- **Deletion in progress**
- **Deletion failed**


If the organization is set as an MSP, a blue icon will be shown next to its name.

Organizations						
DST						
☐	Name of the organization	Status	Status changed	Owner	Location	Lenovo Customer Number
☐	DST Active	🟢	4 day(s) ago	rcurt+iscream@lenovo.com vgont+iscream@lenovo.com sstanclu+iscream@lenovo.com See more	Italy	123
☐	DST Disabled	🔴	2 day(s) ago	rcurt+1@lenovo.com mtucunete+1@lenovo.com sstanclu+16@lenovo.com See more	Argentina	1111
☐	DST MSP 	🟢	11 day(s) ago	mtucunete+1@lenovo.com rcurt+iscream@lenovo.com vgont+iscream@lenovo.com See more	Argentina	123
☐	DST Pending	🟡	2 minute(s) ago	mtucunete+1@lenovo.com	Albania	123

Pending organizations

The following actions can be taken after selecting a pending organization:



- **Edit:** name, location, customer number, MSP
- **Add owner:** a new account will be created, and the user will receive an email to configure it
- **Resend invitation:** the email invitation will be resent (the previous invitation could have expired)
- **Delete:** delete the organization and its database



Active organizations

The following actions can be taken after selecting an active organization:

- **Edit:** name, location, customer number, MSP
- **Add owner:** a new account will be created, and the user will receive an email to configure it
- **Delete:** delete the organization and its database
- **Disable organization:**
 - All users will lose access to the organization
 - It can be easily re-enabled
- **Emergency shutdown:** refer to the next slide for more information



Emergency shutdown

If there is a critical incident, work through the following steps to shut down an organization.


Step 1

1. Understand the implications of this action:

- Most of the users will lose access to the organization
- All hubs will be disabled

Step 2

Step 3



The screenshot shows the 'Emergency' settings page. On the left, under the 'Emergency' heading, there are three radio button options: 'Disable users and hubs' (selected), 'Enable owners', and 'Confirmation'. The main content area is titled 'Disable users and hubs' and contains the following text: 'You can quickly shutdown your organization in the event of a security emergency, such as a security breach or a compromised organization owner.' Below this is a yellow warning box with a triangle icon and the text: 'When you perform an emergency shut down:'. The warning box lists three bullet points: 'All management hubs that are managed by the organization are disabled, which blocks communication between the managed devices, management hubs, and XClarity One.', 'All users are disabled from accessing the organization (except one or more organization owners). User's access to other organizations is not affected.', and 'Users in the pending state for the organization are deleted.' Below the warning box, there is a paragraph: 'After disabling all users and management hubs, you must enable one organization owner. Then, after resolving any security issues that you have in your organization, the organization owner can enable all users and management hubs to return to normal operation.' At the bottom of the main content area, there is a checkbox labeled 'Disable all users and hubs.' which is checked. At the bottom of the page, there are three buttons: 'Cancel' (with a magnifying glass icon), 'Back', and 'Next'.

Emergency shutdown

If there is a critical incident, work through the following steps to shut down an organization.

Step 1

Step 2

Step 3

2. Decide who will be enabled:

An enabled owner will have ability to enable hubs and users one by one. You can select an active owner or send an invitation to a new person.



Emergency

☒ Disable users and hubs

☐ Enable owners

☐ Confirmation

Enable owners

At least one organization owner must be enabled so that users and management hubs can be re-enabled after the issue that caused the emergency shutdown is resolved. Choose from the list of current organization owners, or add a new organization owner.

☐	Name	Email
☐	Alina Tocunete	mtocunete+1@lenovo.com

0 selected

Items displayed: 10

1 - 1 of 1

☒ Or send an invitation to a new user.

Emergency shutdown


If there is a critical incident, work through the following steps to shut down an organization.

Step 1

Step 2

Step 3

3. Review and confirm



The screenshot shows a confirmation dialog for an emergency shutdown. On the left, under the heading "Emergency", there is a list of actions: "Disable users and hubs" (checked), "Enable owners" (checked), and "Confirmation" (selected with a blue circle). On the right, under the heading "Confirmation", there is a warning: "All management hubs and users in the specified organization will be disabled. Only the listed users (organization owners) will remain active." Below this, there are two fields: "Organization name : DST Active" and "Users that will be active : mtucunete+1@lenovo.com". At the bottom, there are three buttons: "Cancel" (with a magnifying glass icon), "Back", and "Finish".

Emergency

- ✓ Disable users and hubs
- ✓ Enable owners
- Confirmation

Confirmation

All management hubs and users in the specified organization will be disabled. Only the listed users (organization owners) will remain active.

Organization name : DST Active


Users that will be active : mtucunete+1@lenovo.com

Cancel Back Finish

Disabled organizations

In the event that an organization is disabled, all organization owners will receive an email.


- Pending users will be removed from the organization.
- Active users will receive the new Disabled Organization status.
- Disabled users will remain disabled.



Re-enabled organizations

In the event that an organization is re-enabled, all organization owners will receive an email.

- Users with the Disabled Organization status will become active.
- Disabled users will remain disabled.




Portal monitoring – events and jobs

Any portal user can see the list of audit and system events. In addition, the Organization Administrator can see the jobs at the portal level. It can be selected from **Monitor** in the right-side context menu.

In the **Events** table, the user can monitor organization events or authentication events from within the last 24 hours.

In the **Jobs** table, the administrator can monitor the status of jobs by clicking **See jobs**.




Deleting an organization

The organization administrator can monitor the status of organization deletion in the jobs table. When an organization is deleted, its entities will also be deleted. This includes:

- Users
- Hubs
- Metrics
- Database

If the deletion job is not completed within three days, the job will be marked as expired, and the organization's status will change to 'Deletion Failed.'



Portal / Monitor / Jobs / Deleting organization Org_to_be_deleted		
Deleting organization Org_to_be_deleted		
Search for anything		
Job	Progress	Resource
Deleting organization Org_to_be_deleted	Created: 10/06/2024 - 15:23:05 Complete: 10/06/2024 - 15:23:13	---
Deleting users for organization Org_to_be_deleted	Created: 10/06/2024 - 15:23:05 Complete: 10/06/2024 - 15:23:06	---
Removing hubs for organization Org_to_be_deleted	Created: 10/06/2024 - 15:23:05 Complete: 10/06/2024 - 15:23:06	---
Removing hub PicoHub	Created: 10/06/2024 - 15:23:05 Complete: 10/06/2024 - 15:23:06	---
Deleting metrics for organization Org_to_be_deleted	Created: 10/06/2024 - 15:23:05 Complete: 10/06/2024 - 15:23:07	---
Deleting database for organization Org_to_be_deleted	Created: 10/06/2024 - 15:23:05 Complete: 10/06/2024 - 15:23:13	---