```
entry
```

L0 (node, purple):
```
L0
LINENUMBER 227 L0
LDC "f4169561-b4ff-4faf-b955-76ebec6ed20a"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.enter (Ljava/lang/String;)V
ALOAD 0
INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.open ()V
L1
LINENUMBER 228 L1
ALOAD 0
GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.preload : Z
IFEQ L2
```

L3 (node):
```
L3
LINENUMBER 229 L3
ALOAD 0
GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.db : Lcom/sleepycat/je/Database;
ACONST_NULL
INVOKEVIRTUAL com/sleepycat/je/Database.preload (Lcom/sleepycat/je/PreloadConfig;)Lcom/sleepycat/je/PreloadStats;
POP
```

L2 (node):
```
L2
LINENUMBER 231 L2
FRAME SAME
INVOKESTATIC java/lang/System.currentTimeMillis ()J
L2D
DSTORE 1
L4
LINENUMBER 232 L4
GETSTATIC com/sleepycat/analysis/MeasureDiskOrderedScan$1.$SwitchMap$com$sleepycat$analysis$MeasureDiskOrderedScan$Action : [I
ALOAD 0
GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.action : Lcom/sleepycat/analysis/MeasureDiskOrderedScan$Action;
INVOKEVIRTUAL com/sleepycat/analysis/MeasureDiskOrderedScan$Action.ordinal ()I
IALOAD
TABLESWITCH 1: L5 2: L6 3: L7 default: L8
```

L5 (node):
```
L5
LINENUMBER 234 L5
FRAME APPEND [D]
ALOAD 0
INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.populate ()V
L9
LINENUMBER 235 L9
GOTO L10
```

L7 (node):
```
L7
LINENUMBER 240 L7
FRAME SAME
ALOAD 0
INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.diskOrderedScan ()V
L12
LINENUMBER 241 L12
GOTO L10
```

L6 (node):
```
L6
LINENUMBER 237 L6
FRAME SAME
ALOAD 0
INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.dirtyReadScan ()V
L11
LINENUMBER 238 L11
GOTO L10
```

L8 (node):
```
L8
LINENUMBER 243 L8
FRAME SAME
ALOAD 0
ALOAD 0
GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.action : Lcom/sleepycat/analysis/MeasureDiskOrderedScan$Action;
INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.fail (Ljava/lang/Object;)V
```

L10 (node, purple):
```
L10
LINENUMBER 245 L10
FRAME SAME
INVOKESTATIC java/lang/System.currentTimeMillis ()J
L2D
DSTORE 3
L13
LINENUMBER 246 L13
DLOAD 3
DLOAD 1
DSUB
LDC 1000.0
DDIV
DSTORE 5
L14
LINENUMBER 247 L14
ALOAD 0
GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.nRecords : I
I2D
DLOAD 5
DDIV
DSTORE 7
L15
LINENUMBER 248 L15
GETSTATIC java/lang/System.out : Ljava/io/PrintStream;
NEW java/lang/StringBuilder
DUP
INVOKESPECIAL java/lang/StringBuilder.<init> ()V
                                    LDC "
Total seconds: "
INVOKEVIRTUAL java/lang/StringBuilder.append (Ljava/lang/String;)Ljava/lang/StringBuilder;
DLOAD 5
INVOKEVIRTUAL java/lang/StringBuilder.append (D)Ljava/lang/StringBuilder;
LDC " txn/sec: "
INVOKEVIRTUAL java/lang/StringBuilder.append (Ljava/lang/String;)Ljava/lang/StringBuilder;
DLOAD 7
INVOKEVIRTUAL java/lang/StringBuilder.append (D)Ljava/lang/StringBuilder;
INVOKEVIRTUAL java/lang/StringBuilder.toString ()Ljava/lang/String;
INVOKEVIRTUAL java/io/PrintStream.println (Ljava/lang/String;)V
L16
LINENUMBER 249 L16
ALOAD 0
INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.close ()V
L17
LINENUMBER 250 L17
LDC "f4169561-b4ff-4faf-b955-76ebec6ed20a"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
RETURN
L18
```

```
exit
```