```
entry
                                                                                                                         LINENUMBER 389 L0
                                                                                                                         ALOAD 0
                                                                                                                          ALOAD 0
                                                                                                                         GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                                                                                                         INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getNodeSequence ()Lcom/sleepycat/je/dbi/NodeSequence;
                                                                                                                         INVOKEVIRTUAL com/sleepycat/je/dbi/NodeSequence.getNextTransientLsn ()J
                                                                                                                         PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.eofLsn: J
                                                                                                                          LINENUMBER 391 L1
                                                                                                                         GETSTATIC com/sleepycat/je/dbi/DatabaseImpl.$assertionsDisabled : Z
                                                                                                                                                                      ALOAD 0
                                                                                                                                                                     INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.replicatedBitSet ()Z
                                                                                                                                                                     IFEQ L2
                                                                                                                                                                             ALOAD 0
                                                                                                                                                                            INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.notReplicatedBitSet ()Z
                                                                                                                                                                            IFEQ L2
                                                                                                  LINENUMBER 409 L2
                                                                                                  FRAME SAME
                                                                                                  ALOAD 0
                                                                                                  GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager;
                                                                                                  ASTORE 1
                                                                                                  L3
                                                                                                  LINENUMBER 411 L3
                                                                                                  ALOAD 0
                                                                                                  ALOAD 1
                                                                                                  GETSTATIC com/sleepycat/je/config/EnvironmentParams.BIN_DELTA_PERCENT: Lcom/sleepycat/je/config/IntConfigParam;
                                                                                                  LINENUMBER 412 L4
                                                                                                  INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.binDeltaPercent : I
                                                                                                  LINENUMBER 420 L5
                                                                                                  ALOAD 0
                                                                                                  GETFIELD com/sleepycat/je/dbi/DatabaseImpl.maxTreeEntriesPerNode: I
                                                                                                  IFNE L6
                                                                                                        LINENUMBER 421 L7
                                                                                                                                                                                                                                    NEW java/lang/AssertionError
                                                                                                        ALOAD 0
                                                                                                        ALOAD 1
                                                                                                                                                                                                                                   DUP
                                                                                                                                                                                                                                  LDC "The replicated AND notReplicated bits should never be set together" INVOKESPECIAL java/lang/AssertionError.<init> (Ljava/lang/Object;)V ATHROW
                                                                                                        GETSTATIC com/sleepycat/je/config/EnvironmentParams.NODE_MAX: Lcom/sleepycat/je/config/IntConfigParam;
                                                                                                        LINENUMBER 422 L8
                                                                                                       INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.maxTreeEntriesPerNode: I
                                                                                   LINENUMBER 426 L6
                                                                                   FRAME APPEND [com/sleepycat/je/dbi/DbConfigManager]
                                                                                   ALOAD 0
                                                                                   GETFIELD com/sleepycat/je/dbi/DatabaseImpl.dbFileSummaries: Lcom/sleepycat/je/cleaner/DbFileSummaryMap;
                                                                                   ALOAD 0
                                                                                   GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/cleaner/DbFileSummaryMap.init (Lcom/sleepycat/je/dbi/EnvironmentImpl;)V
                                                                                   LINENUMBER 435 L9
                                                                                   ALOAD 0
                                                                                   INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl.getUtilizationRepairDone ()Z
                                                                                   IFNE L10
                                                                                                                                      LINENUMBER 436 L11
                                                                                                                                      ALOAD 0
                                                                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.dbFileSummaries: Lcom/sleepycat/je/cleaner/DbFileSummaryMap;
                                                                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/cleaner/DbFileSummaryMap.repair (Lcom/sleepycat/je/dbi/EnvironmentImpl;)V
                                                                                                                                     LINENUMBER 437 L12
                                                                                                                                      ALOAD 0
                                                                                                                                      INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl.setDirty ()V
                                                                                                                                     LINENUMBER 438 L13
                                                                                                                                      ALOAD 0
                                                                                                                                      INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.setUtilizationRepairDone ()V
                                                                                                                                        LINENUMBER 442 L10
                                                                                                                                         FRAME SAME
                                                                                                                                         ALOAD 0
                                                                                                                                         GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getNoComparators ()Z
                                                                                                                                         IFNE L14
                                                                                                 L15
                                                                                                 LINENUMBER 444 L15
                                                                                                 NEW com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader
                                                                                                 DUP
                                                                                                 ALOAD 0
                                                                                                 GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparatorBytes: [B
                                                                                                 LDC "Btree"
                                                                                                 ALOAD 0
                                                                                                 GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                                                                                 LINENUMBER 445 L16
                                                                                                 INVOKEVIRTUAL\ com/sleepycat/je/dbi/EnvironmentImpl.getClassLoader\ () Liava/lang/ClassLoader;
                                                                                                 INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.<init> ([BLjava/lang/String;Ljava/lang/ClassLoader;)V
                                                                                                 ASTORE 2
                                                                                                 L17
                                                                                                 LINENUMBER 446 L17
                                                                                                 ALOAD 0
                                                                                                 ALOAD 2
                                                                                                 INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.getComparator()Ljava/util/Comparator; PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator: Ljava/util/Comparator;
                                                                                                 LINENUMBER 447 L18
                                                                                                 ALOAD 0
                                                                                                 ALOAD 2
                                                                                                 INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.isClass ()Z PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparatorByClassName : Z
                                                                                                 LINENUMBER 448 L19
                                                                                                 ALOAD 0
                                                                                                 ALOAD 0
                                                                                                 GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator : Ljava/util/Comparator; INSTANCEOF com/sleepycat/je/PartialComparator
                                                                                                 PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreePartialComparator: Z
                                                                                                 LINENUMBER 450 L20
ALOAD 0
                                                                                                 ALOAD 0
                                                                                                 GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator: Ljava/util/Comparator;
                                                                                                 IFNULL L21
                                                                                                                      ALOAD 0
                                                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator : Ljava/util/Comparator; INSTANCEOF com/sleepycat/je/BinaryEqualityComparator
                                                                                                                     IFEQ L22
FRAME FULL [com/sleepycat/je/dbi/DatabaseImpl com/sleepycat/je/dbi/DbConfigManager com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader] [com/sleepycat/je/dbi/DatabaseImpl]
                                                                                                                                                                                                 FRAME SAME1 com/sleepycat/je/dbi/DatabaseImpl
ICONST_1
                                                                                                                                                                                                ICONST_0
GOTO L23
                            FRAME FULL [com/sleepycat/je/dbi/DatabaseImpl com/sleepycat/je/dbi/DbConfigManager com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader] [com/sleepycat/je/dbi/DatabaseImpl I] PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeBinaryEqualityComparator: Z
                            LINENUMBER 454 L24
                            NEW com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader
                            DUP
                            ALOAD 0
                            GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparatorBytes: [B
                            LDC "Duplicate"
                            ALOAD 0
                            GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                            LINENUMBER 456 L25
                            INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getClassLoader ()Ljava/lang/ClassLoader; INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.<init> ([BLjava/lang/String;Ljava/lang/ClassLoader;)V
                            ASTORE 2
                            L26
                            LINENUMBER 457 L26
                            ALOAD 0
                            ALOAD 2
                            INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.getComparator ()Ljava/util/Comparator;
                            PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator: Ljava/util/Comparator;
                            LINENUMBER 458 L27
                            ALOAD 0
                            ALOAD 2
                            INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.isClass ()Z PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparatorByClassName : Z
                            LINENUMBER 459 L28
                            ALOAD 0
                            ALOAD 0
                            GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator : Ljava/util/Comparator;
                            INSTANCEOF com/sleepycat/je/PartialComparator
                            PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicatePartialComparator : Z
                            LINENUMBER 461 L29
                            ALOAD 0
                            ALOAD 0
                            GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator : Ljava/util/Comparator;
                            IFNULL L30
                                                                                                                              ALOAD 0
                                                                                                                             GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator : Ljava/util/Comparator;
                                                                                                                             INSTANCEOF com/sleepycat/je/BinaryEqualityComparator
                                                                                                                             IFEQ L31
                                                                                            FRAME SAME1 com/sleepycat/je/dbi/DatabaseImpl
                                                                                                                                                       FRAME SAME1 com/sleepycat/je/dbi/DatabaseImpl
                                                                                            ICONST_1
                                                                                                                                                       ICONST_0
                                                                                            GOTO L\overline{3}2
                                                         FRAME FULL [com/sleepycat/je/dbi/DatabaseImpl com/sleepycat/je/dbi/DbConfigManager com/sleepycat/je/dbi/DatabaseImpl [com/sleepycat/je/dbi/DatabaseImpl I]
                                                         PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateBinaryEqualityComparator : Z
                                                          L33
                                                         LINENUMBER 466 L33
                                                          ALOAD 0
                                                          INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.resetKeyComparator ()V
                                                                                                                                                                                                                                         L14
                                                                                                                                                                                                                                         LINENUMBER 468 L14
                                                                                                                                                                                                                                         FRAME CHOP 1
                                                                                                                                                                                                                                         RETURN
                                                                                                                                                                                                                                         L34
```

exit