```
entry
                              LINENUMBER 389 L0
                               ALOAD 0
                              ALOAD 0
                              GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getNodeSequence ()Lcom/sleepycat/je/dbi/NodeSequence; INVOKEVIRTUAL com/sleepycat/je/dbi/NodeSequence.getNextTransientLsn ()J
                              PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.eofLsn: J
                               LINENUMBER 391 L1
                               GETSTATIC com/sleepycat/je/dbi/DatabaseImpl.$assertionsDisabled : Z
                               ALOAD 0
                              INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.replicatedBitSet ()Z
                              IFEQ L2
                    ALOAD 0
                    INVOKESPECIAL\ com/sleepycat/je/dbi/DatabaseImpl.notReplicatedBitSet\ () Z
                   IFEQ L2
                                             LINENUMBER 409 L2
                                             FRAME SAME
                                             ALOAD 0
                                             GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager;
                                             ASTORE 1
                                             L3
                                             LINENUMBER 411 L3
                                             ALOAD 0
                                             ALOAD 1
                                             GETSTATIC com/sleepycat/je/config/EnvironmentParams.BIN_DELTA_PERCENT: Lcom/sleepycat/je/config/IntConfigParam;
                                             LINENUMBER 412 L4
                                             INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.binDeltaPercent : I
                                             LINENUMBER 420 L5
                                             ALOAD 0
                                             GETFIELD com/sleepycat/je/dbi/DatabaseImpl.maxTreeEntriesPerNode: I
                                             IFNE L6
                                                                                                       LINENUMBER 421 L7
 NEW java/lang/AssertionError
                                                                                                       ALOAD 0
                                                                                                       ALOAD 1
LDC "The replicated AND notReplicated bits should never be set together" INVOKESPECIAL java/lang/AssertionError.<init> (Ljava/lang/Object;)V ATHROW
                                                                                                        GETSTATIC com/sleepycat/je/config/EnvironmentParams.NODE_MAX: Lcom/sleepycat/je/config/IntConfigParam;
                                                                                                        LINENUMBER 422 L8
                                                                                                       INVOKEVIRTUAL com/sleepycat/je/dbi/DbConfigManager.getInt (Lcom/sleepycat/je/config/IntConfigParam;)I PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.maxTreeEntriesPerNode: I
                                                                                   LINENUMBER 426 L6
                                                                                   FRAME APPEND [com/sleepycat/je/dbi/DbConfigManager]
                                                                                   ALOAD 0
                                                                                   GETFIELD com/sleepycat/je/dbi/DatabaseImpl.dbFileSummaries: Lcom/sleepycat/je/cleaner/DbFileSummaryMap;
                                                                                   ALOAD 0
                                                                                   GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/cleaner/DbFileSummaryMap.init (Lcom/sleepycat/je/dbi/EnvironmentImpl;)V
                                                                                   LINENUMBER 435 L9
                                                                                   ALOAD 0
                                                                                   INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl.getUtilizationRepairDone ()Z
                                                                                   IFNE L10
                                                             LINENUMBER 436 L11
                                                              ALOAD 0
                                                             GETFIELD com/sleepycat/je/dbi/DatabaseImpl.dbFileSummaries: Lcom/sleepycat/je/cleaner/DbFileSummaryMap;
                                                             GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/cleaner/DbFileSummaryMap.repair (Lcom/sleepycat/je/dbi/EnvironmentImpl;)V
                                                              LINENUMBER 437 L12
                                                              ALOAD 0
                                                              INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl.setDirty ()V
                                                             LINENUMBER 438 L13
                                                              ALOAD 0
                                                              INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.setUtilizationRepairDone ()V
                                                                                LINENUMBER 442 L10
                                                                                FRAME SAME
                                                                                ALOAD 0
                                                                                GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl; INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getNoComparators ()Z
                                                                                IFNE L14
                                                                         LINENUMBER 444 L15
                                                                        NEW com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader
                                                                        DUP
                                                                        ALOAD 0
                                                                        GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparatorBytes: [B
                                                                        LDC "Btree"
                                                                        ALOAD 0
                                                                        GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                                                        LINENUMBER 445 L16
                                                                        INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getClassLoader ()Ljava/lang/ClassLoader;
                                                                        INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.<init> ([BLjava/lang/String;Ljava/lang/ClassLoader;)V
                                                                        ASTORE 2
                                                                        L17
                                                                        LINENUMBER 446 L17
                                                                        ALOAD 0
                                                                        ALOAD 2
                                                                        INVOKEVIRTUAL\ com/sleepycat/je/dbi/DatabaseImpl\$ComparatorReader.getComparator\ () Ljava/util/Comparator;
                                                                        PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator: Ljava/util/Comparator;
                                                                        LINENUMBER 447 L18
                                                                        ALOAD 0
                                                                        ALOAD 2
                                                                        INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.isClass ()Z
                                                                        PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparatorByClassName: Z
                                                                        LINENUMBER 448 L19
                                                                        ALOAD 0
                                                                        ALOAD 0
                                                                        GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator : Ljava/util/Comparator; INSTANCEOF com/sleepycat/je/PartialComparator PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreePartialComparator : Z
                                                                        LINENUMBER 450 L20
ALOAD 0
                                                                        ALOAD 0
                                                                        GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator: Ljava/util/Comparator;
                                                                         IFNULL L21
                                                                                                                                                  ALOAD 0
                                                                                                                                                 GETFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeComparator : Ljava/util/Comparator; INSTANCEOF com/sleepycat/je/BinaryEqualityComparator
                                                                                                                                                 IFEQ L22
                                                                                                                                                                                                                                                             L22
FRAME SAME1 com/sleepycat/je/dbi/DatabaseImpl
                                                          FRAME FULL [com/sleepycat/je/dbi/DatabaseImpl com/sleepycat/je/dbi/DbConfigManager com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader] [com/sleepycat/je/dbi/DatabaseImpl]
                                                          ICONST_1
                                                                                                                                                                                                                                                              ICONST_0
                                                          GOTO L23
                                                                                     FRAME FULL [com/sleepycat/je/dbi/DatabaseImpl com/sleepycat/je/dbi/DbConfigManager com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader] [com/sleepycat/je/dbi/DatabaseImpl I] PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.btreeBinaryEqualityComparator: Z
                                                                                     LINENUMBER 454 L24
                                                                                     NEW com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader
                                                                                     DUP
                                                                                     ALOAD 0
                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparatorBytes: [B
                                                                                     LDC "Duplicate"
                                                                                     ALOAD Ô
                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.envImpl: Lcom/sleepycat/je/dbi/EnvironmentImpl;
                                                                                     LINENUMBER 456 L25
                                                                                     INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getClassLoader ()Ljava/lang/ClassLoader; INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.<init> ([BLjava/lang/String;Ljava/lang/ClassLoader;)V
                                                                                     ASTORE 2
                                                                                     L26
                                                                                     LINENUMBER 457 L26
                                                                                     ALOAD 0
                                                                                     ALOAD 2
                                                                                     INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.getComparator ()Ljava/util/Comparator;
                                                                                     PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator: Ljava/util/Comparator;
                                                                                     LINENUMBER 458 L27
                                                                                     ALOAD 0
                                                                                     ALOAD 2
                                                                                     INVOKEVIRTUAL com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader.isClass ()Z PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparatorByClassName : Z
                                                                                     LINENUMBER 459 L28
                                                                                     ALOAD 0
                                                                                     ALOAD 0
                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator : Ljava/util/Comparator;
                                                                                     INSTANCEOF com/sleepycat/je/PartialComparator
                                                                                     PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicatePartialComparator : Z
                                                                                     LINENUMBER 461 L29
                                                                                     ALOAD 0
                                                                                     ALOAD 0
                                                                                     GETFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator : Ljava/util/Comparator;
                                                                                     IFNULL L30
                                                                                                                                                   ALOAD 0
                                                                                                                                                   GETFIELD\ com/sleepycat/je/dbi/DatabaseImpl.duplicateComparator: Ljava/util/Comparator;
                                                                                                                                                   INSTANCEOF com/sleepycat/je/BinaryEqualityComparator
                                                                                                                                                   IFEQ L31
                                                                                                                 L30
                                                                                                                 FRAME SAME1 com/sleepycat/je/dbi/DatabaseImpl
                                                                                                                                                                             FRAME SAME1 com/sleepycat/je/dbi/DatabaseImpl
                                                                                                                 ICONST_1
                                                                                                                                                                             ICONST_0
                                                                                                                 GOTO L\overline{3}2
                                                          FRAME FULL [com/sleepycat/je/dbi/DatabaseImpl com/sleepycat/je/dbi/DbConfigManager com/sleepycat/je/dbi/DatabaseImpl$ComparatorReader] [com/sleepycat/je/dbi/DatabaseImpl I]
                                                          PUTFIELD com/sleepycat/je/dbi/DatabaseImpl.duplicateBinaryEqualityComparator : Z
                                                          L33
                                                          LINENUMBER 466 L33
                                                          ALOAD 0
                                                          INVOKESPECIAL com/sleepycat/je/dbi/DatabaseImpl.resetKeyComparator ()V
                                             LINENUMBER 468 L14
                                             FRAME CHOP 1
                                             RETURN
                                             L34
```

exit