```
entry
```

```
L0
LINENUMBER 234 L0
ALOAD 0
INVOKESPECIAL java/lang/Object.<init> ()V
L1
LINENUMBER 188 L1
ALOAD 0
ICONST_0
PUTFIELD com/sleepycat/je/Cursor.nonSticky : Z
L2
LINENUMBER 236 L2
ALOAD 3
IFNONNULL L3
```

```
L4
LINENUMBER 237 L4
GETSTATIC com/sleepycat/je/CursorConfig.DEFAULT : Lcom/sleepycat/je/CursorConfig;
ASTORE 3
```

```
L3
LINENUMBER 241 L3
FRAME FULL [com/sleepycat/je/Cursor com/sleepycat/je/Database com/sleepycat/je/txn/Locker com/sleepycat/je/CursorConfig] []
ALOAD 1
INVOKEVIRTUAL com/sleepycat/je/Database.checkOpen ()Lcom/sleepycat/je/dbi/DatabaseImpl;
ASTORE 4
L5
LINENUMBER 243 L5
ALOAD 1
ALOAD 2
ALOAD 3
L6
LINENUMBER 244 L6
INVOKEVIRTUAL com/sleepycat/je/CursorConfig.getReadCommitted ()Z
L7
LINENUMBER 243 L7
INVOKESTATIC com/sleepycat/je/txn/LockerFactory.getReadableLocker (Lcom/sleepycat/je/Database;Lcom/sleepycat/je/txn/Locker;Z)Lcom/sleepycat/je/txn/Locker;
ASTORE 2
L8
LINENUMBER 246 L8
ALOAD 0
ALOAD 1
ALOAD 4
ALOAD 2
ALOAD 3
ICONST_0
INVOKESPECIAL com/sleepycat/je/Cursor.init (Lcom/sleepycat/je/Database;Lcom/sleepycat/je/dbi/DatabaseImpl;Lcom/sleepycat/je/txn/Locker;Lcom/sleepycat/je/CursorConfig;Z)V
L9
LINENUMBER 248 L9
RETURN
L10
```

```
exit
```