

```
LINENUMBER 91 L0
LDC "45aee721-7a9f-4d2e-8d64-c4cb4d9f76d4"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.enter (Ljava/lang/String;)V
ALOAD 0
ALOAD 1
ILOAD 2
ILOAD 3
ICONST 1
INVOKESPECIAL java/util/logging/FileHandler.<init> (Ljava/lang/String;IIZ)V
LINENUMBER 93 L1
NEW com/sleepycat/je/util/FileHandler$1
DUP
ALOAD 0
INVOKESPECIAL com/sleepycat/je/util/FileHandler$1.<init> (Lcom/sleepycat/je/util/FileHandler;)V
ASTORE 6
LINENUMBER 103 L2
ALOAD 0
ALOAD 6
INVOKEVIRTUAL com/sleepycat/je/util/FileHandler.setErrorManager (Ljava/util/logging/ErrorManager;)V
LINENUMBER 106 L3
ALOAD 0
ALOAD 4
INVOKEVIRTUAL com/sleepycat/je/util/FileHandler.setFormatter (Ljava/util/logging/Formatter;)V
LINENUMBER 108 L4
ALOAD 5
LINENUMBER 109 L5
INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.getConfigManager ()Lcom/sleepycat/je/dbi/DbConfigManager;
GETSTATIC com/sleepycat/je/config/EnvironmentParams.JE_FILE_LEVEL: Lcom/sleepycat/je/config/ConfigParam;
NEW java/lang/StringBuilder
DUP
INVOKESPECIAL java/lang/StringBuilder.<init>()V
ALOAD 0
L6
LINENUMBER 110 L6
INVOKEVIRTUAL java/lang/Object.getClass ()Ljava/lang/Class;
INVOKEVIRTUAL java/lang/Class.getName ()Ljava/lang/String;
INVOKEVIRTUAL java/lang/StringBuilder.append (Ljava/lang/String;)Ljava/lang/StringBuilder;
LDC ".level"
INVOKEVIRTUAL java/lang/StringBuilder.append (Ljava/lang/String;)Ljava/lang/StringBuilder;
INVOKEVIRTUAL java/lang/StringBuilder.toString ()Ljava/lang/String;
LINENUMBER 109 L7
INVOKESTATIC com/sleepycat/je/utilint/LoggerUtils.getHandlerLevel (Lcom/sleepycat/je/dbi/DbConfigManager;Lcom/sleepycat/je/configParam;Ljava/lang/String;)Ljava/util/logging/Level;
ASTORE 7
LINENUMBER 112 L8
ALOAD 0
ALOAD 7
INVOKEVIRTUAL com/sleepycat/je/util/FileHandler.setLevel (Ljava/util/logging/Level;)V
LINENUMBER 113 L9
LDC "45aee721-7a9f-4d2e-8d64-c4cb4d9f76d4"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
RETURN
L10
```