```
LINENUMBER 356 L0
                                                                                                             LDC "2347a8ec-c8a9-46d9-9270-b701eb02bdaa"
                                                                                                             INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.enter (Ljava/lang/String;)V
                                                                                                             NEW com/sleepycat/je/DatabaseEntry
                                                                                                             INVOKESPECIAL com/sleepycat/je/DatabaseEntry.<init> ()V
                                                                                                             ASTORE 1
                                                                                                            LINENUMBER 357 L1
                                                                                                             NEW com/sleepycat/je/DatabaseEntry
                                                                                                             INVOKESPECIAL com/sleepycat/je/DatabaseEntry.<init> ()V
                                                                                                             ASTORE 2
                                                                                                            LINENUMBER 358 L2
                                                                                                             NEW com/sleepycat/je/DiskOrderedCursorConfig
                                                                                                             INVOKESPECIAL com/sleepycat/je/DiskOrderedCursorConfig.<init>()V
                                                                                                             ASTORE 3
                                                                                                            LINENUMBER 359 L3
                                                                                                             ALOAD 3
                                                                                                             ALOAD 0
                                                                                                            GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.keysOnly: Z
                                                                                                             INVOKEVIRTUAL com/sleepycat/je/DiskOrderedCursorConfig.setKeysOnly (Z)Lcom/sleepycat/je/DiskOrderedCursorConfig;
                                                                                                            LINENUMBER 360 L4
                                                                                                             ALOAD 3
                                                                                                             ALOAD 0
                                                                                                             GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.internalMemoryLimit: J
                                                                                                            INVOKEVIRTUAL com/sleepycat/je/DiskOrderedCursorConfig.setInternalMemoryLimit (J)Lcom/sleepycat/je/DiskOrderedCursorConfig;
                                                                                                            LINENUMBER 361 L5
                                                                                                             ALOAD 3
                                                                                                             ALOAD 0
                                                                                                            GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.lsnBatchSize: J
                                                                                                             INVOKEVIRTUAL com/sleepycat/je/DiskOrderedCursorConfig.setLSNBatchSize (J)Lcom/sleepycat/je/DiskOrderedCursorConfig;
                                                                                                            LINENUMBER 362 L6
                                                                                                             ALOAD 0
                                                                                                            GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.db: Lcom/sleepycat/je/Database;
                                                                                                             INVOKEVIRTUAL com/sleepycat/je/Database.openCursor (Lcom/sleepycat/je/DiskOrderedCursorConfig;)Lcom/sleepycat/je/DiskOrderedCursor;
                                                                                                             ASTORE 4
                                                                                                             LINENUMBER 363 L7
                                                                                                             ICONST 0
                                                                                                             ISTORE 5
                                                                            LINENUMBER 364 L8
                                                                            FRAME FULL [com/sleepycat/analysis/MeasureDiskOrderedScan com/sleepycat/je/DatabaseEntry com/sleepycat/je/DatabaseEntry com/sleepycat/je/DiskOrderedCursorConfig com/sleepycat/je/DiskOrderedCursor I] []
                                                                            ALOAD 1
ALOAD 2
                                                                            GETSTATIC com/sleepycat/je/LockMode.READ_UNCOMMITTED: Lcom/sleepycat/je/LockMode; INVOKEVIRTUAL com/sleepycat/je/DiskOrderedCursor.getNext (Lcom/sleepycat/je/DatabaseEntry;Lcom/sleepycat/je/DatabaseEntry;Lcom/sleepycat/je/LockMode;)Lcom/sleepycat/je/OperationStatus; GETSTATIC com/sleepycat/je/OperationStatus.SUCCESS: Lcom/sleepycat/je/OperationStatus;
                                                                            IF_ACMPNE L9
LINENUMBER 371 L9
FRAME SAME
ALOAD 4
INVOKEVIRTUAL com/sleepycat/je/DiskOrderedCursor.close ()V
                                                                                                                        L10
                                                                                                                        LINENUMBER 365 L10
LINENUMBER 372 L14
                                                                                                                        ALOAD 0
ALOAD 0
                                                                                                                        ALOAD 1
ALOAD 0
GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.nRecords: I
                                                                                                                        INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.checkAnyKey (Lcom/sleepycat/je/DatabaseEntry;)V
INVOKESTATIC java/lang/Integer.valueOf (I)Ljava/lang/Integer;
                                                                                                                        LINENUMBER 366 L11 ALOAD 0
ILOAD 5
INVOKESTATIC java/lang/Integer.valueOf (I)Ljava/lang/Integer; INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.checkEquals (Ljava/lang/Object;Ljava/lang/Object;)V
                                                                                                                        GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.keysOnly: Z
                                                                                                                        IFNE L12
LINENUMBER 373 L15
LDC "2347a8ec-c8a9-46d9-9270-b701eb02bdaa"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
RETURN
L16
                                                                                                                     LINENUMBER 367 L13
                                                                                                                     ALOAD 0
                                                       exit
                                                                                                                     ALOAD 2
                                                                                                                     INVOKESPECIAL com/sleepycat/analysis/MeasureDiskOrderedScan.checkData (Lcom/sleepycat/je/DatabaseEntry;)V
                                                                                                                                                                                                                             L12
                                                                                                                                                                                                                             LINENUMBER 369 L12
                                                                                                                                                                                                                             FRAME SAME
                                                                                                                                                                                                                             IINC 5 1
                                                                                                                                                                                                                            GOTO L8
```

entry