
entry
TRYCATCHBLOCK L0 L1 L2 null
TRYCATCHBLOCK L3 L4 L5 com/sleepycat/je/DatabaseException
TRYCATCHBLOCK L3 L4 L6 java/lang/RuntimeException
TRYCATCHBLOCK L7 L8 L9 null
TRYCATCHBLOCK L9 L10 L9 null
L11
LINENUMBER 404 L11
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.enter (Ljava/lang/String;)V
ALOAD 0
GETFIELD com/sleepycat/je/Environment.environmentImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
IFNONNULL L12
L12
LINENUMBER 408 L12
FRAME SAME
ALOAD 0
GETFIELD com/sleepycat/je/Environment.environmentImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.isValid (Z
IFNE L14
L13
LINENUMBER 405 L13
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
RETURN
L14
LINENUMBER 428 L14
FRAME CHOP 1
NEW java/lang/StringBuilder
DUP
INVOKESPECIAL java/lang/StringBuilder.<init> ()V
ASTORE 1
L7
LINENUMBER 430 L7
ALOAD 0
ALOAD 1
INVOKESPECIAL com/sleepycat/je/Environment.checkForCloseErrors (Ljava/lang/StringBuilder;)V
L3
LINENUMBER 433 L3
ALOAD 0
GETFIELD com/sleepycat/je/Environment.environmentImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.close ()V
L4
LINENUMBER 442 L4
GOTO L26
L0
LINENUMBER 417 L0
ALOAD 0
GETFIELD com/sleepycat/je/Environment.environmentImpl : Lcom/sleepycat/je/dbi/EnvironmentImpl;
INVOKEVIRTUAL com/sleepycat/je/dbi/EnvironmentImpl.closeAfterInvalid ()V
L1
LINENUMBER 419 L1
ALOAD 0
INVOKEVIRTUAL com/sleepycat/je/Environment.clearEnvImpl ()V
L15
LINENUMBER 421 L15
ALOAD 0
GETFIELD com/sleepycat/je/Environment.referringDbs : Ljava/util/Map;
INVOKEINTERFACE java/util/Map.keySet (Ljava/util/Set;
INVOKEINTERFACE java/util/Set.iterator (Ljava/util/Iterator;
ASTORE 1
L2
LINENUMBER 419 L2
FRAME FULL [com/sleepycat/je/Environment] [java/lang/Throwable]
ASTORE 3
ALOAD 0
INVOKEVIRTUAL com/sleepycat/je/Environment.clearEnvImpl ()V
L21
LINENUMBER 421 L21
ALOAD 0
GETFIELD com/sleepycat/je/Environment.referringDbs : Ljava/util/Map;
INVOKEINTERFACE java/util/Map.keySet (Ljava/util/Set;
INVOKEINTERFACE java/util/Set.iterator (Ljava/util/Iterator;
ASTORE 4
L26
LINENUMBER 444 L26
FRAME CHOP 1
ALOAD 1
INVOKEVIRTUAL java/lang/StringBuilder.length ()I
IFLE L8
L6
LINENUMBER 437 L6
FRAME SAME1 java/lang/RuntimeException
ASTORE 2
L29
LINENUMBER 438 L29
ALOAD 1
INVOKEVIRTUAL java/lang/StringBuilder.length ()I
IFLE L30
L8
LINENUMBER 448 L8
FRAME SAME
ALOAD 0
INVOKEVIRTUAL com/sleepycat/je/Environment.clearEnvImpl ()V
L33
LINENUMBER 449 L33
GOTO L34
L32
LINENUMBER 445 L32
NEW java/lang/IllegalStateException
DUP
ALOAD 1
INVOKEVIRTUAL java/lang/StringBuilder.toString (Ljava/lang/String;
INVOKESPECIAL java/lang/IllegalStateException.<init> (Ljava/lang/String;)V
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
ATHROW
L30
LINENUMBER 441 L30
FRAME APPEND [java/lang/RuntimeException]
ALOAD 2
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
ATHROW
L31
LINENUMBER 439 L31
NEW java/lang/IllegalStateException
DUP
ALOAD 1
INVOKEVIRTUAL java/lang/StringBuilder.toString (Ljava/lang/String;
ALOAD 2
INVOKESPECIAL java/lang/IllegalStateException.<init> (Ljava/lang/String;Ljava/lang/Throwable;)V
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
ATHROW
L5
LINENUMBER 434 L5
FRAME FULL [com/sleepycat/je/Environment java/lang/StringBuilder] [com/sleepycat/je/DatabaseException]
ASTORE 2
L27
LINENUMBER 435 L27
ALOAD 2
ALOAD 1
INVOKEVIRTUAL java/lang/StringBuilder.toString (Ljava/lang/String;
INVOKEVIRTUAL com/sleepycat/je/DatabaseException.addErrorMessage (Ljava/lang/String;)V
L28
LINENUMBER 436 L28
ALOAD 2
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
ATHROW
L16
FRAME APPEND [java/util/Iterator]
ALOAD 1
INVOKEINTERFACE java/util/Iterator.hasNext (Z
IFEQ L17
L22
FRAME FULL [com/sleepycat/je/Environment T T java/lang/Throwable java/util/Iterator] []
ALOAD 4
INVOKEINTERFACE java/util/Iterator.hasNext (Z
IFEQ L23
L9
LINENUMBER 448 L9
FRAME SAME1 java/lang/Throwable
ASTORE 6
ALOAD 1
INVOKEINTERFACE java/util/Iterator.next (Ljava/lang/Object;
CHECKCAST com/sleepycat/je/Database
ASTORE 2
L18
LINENUMBER 422 L18
ALOAD 2
GETSTATIC com/sleepycat/je/Database$DbState.CLOSED : Lcom/sleepycat/je/Database$DbState;
ACONST_NULL
INVOKEVIRTUAL com/sleepycat/je/Database.minimalClose (Lcom/sleepycat/je/Database$DbState;Lcom/sleepycat/je/OperationFailureException;)V
L19
LINENUMBER 423 L19
GOTO L16
L17
LINENUMBER 424 L17
FRAME SAME
GOTO L20
ALOAD 4
INVOKEINTERFACE java/util/Iterator.next (Ljava/lang/Object;
CHECKCAST com/sleepycat/je/Database
ASTORE 5
L24
LINENUMBER 422 L24
ALOAD 5
GETSTATIC com/sleepycat/je/Database$DbState.CLOSED : Lcom/sleepycat/je/Database$DbState;
ACONST_NULL
INVOKEVIRTUAL com/sleepycat/je/Database.minimalClose (Lcom/sleepycat/je/Database$DbState;Lcom/sleepycat/je/OperationFailureException;)V
L25
LINENUMBER 423 L25
GOTO L22
L34
LINENUMBER 450 L34
FRAME SAME
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
RETURN
L36
L10
ALOAD 0
INVOKEVIRTUAL com/sleepycat/je/Environment.clearEnvImpl ()V
L35
LINENUMBER 449 L35
ALOAD 6
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
ATHROW
L20
LINENUMBER 425 L20
FRAME FULL [com/sleepycat/je/Environment java/util/Iterator] []
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
RETURN
L23
LINENUMBER 424 L23
FRAME SAME
ALOAD 3
LDC "682c8a92-3970-4ad8-8f7e-a862a5bed064"
INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V
ATHROW
exit