```
entry
                                                             LINENUMBER 254 L0
                                                             ALOAD 0
                                                             GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.internalMemoryLimit: J
                                                             LDC 9223372036854775807
                                                             LCMP
                                                             IFEQ L1
                                   ALOAD 0
                                   GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.internalMemoryLimit: J
                                                                                                                       FRAME SAME
                                   GOTO L2
                                                                                                                       LCONST 0
                                                                 FRAME SAME1 J
                                                                 ALOAD 0
                                                                 GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.jeCacheSize: J
                                                                 LADD
                                                                 ALOAD 0
                                                                 GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.jeCacheSize: J
                                                                 LDC 2
                                                                 LDIV
                                                                 LADD
                                                                 LSTORE 1
                                                                 LINENUMBER 259 L3
                                                                 INVOKESTATIC java/lang/Runtime.getRuntime ()Ljava/lang/Runtime;
                                                                 INVOKEVIRTUAL java/lang/Runtime.maxMemory ()J
                                                                 LLOAD 1
                                                                 LCMP
                                                                 IFGE L4
                                                                                            LINENUMBER 266 L4
                                                                                             FRAME APPEND [J]
                                                                                            GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.action: Lcom/sleepycat/analysis/MeasureDiskOrderedScan$Action;
                                                                                             GETSTATIC com/sleepycat/analysis/MeasureDiskOrderedScan$Action.Populate: Lcom/sleepycat/analysis/MeasureDiskOrderedScan$Action;
                                                                                            IF_ACMPNE L6
                                                                                                                                                      L6
                                                                                                                                                                          ICONST_1
                                                                                                                                                      FRAME SAME
                                                                                                                                                                         GOTO L7
                                                                                                                                                      ICONST_0
                                                                                             FRAME SAME1 I
                                                                                             ISTORE 3
                                                                                             LINENUMBER 268 L8
                                                                                             NEW com/sleepycat/je/EnvironmentConfig
                                                                                             INVOKESPECIAL com/sleepycat/je/EnvironmentConfig.<init>()V
                                                                                             ASTORE 4
                                                                                             L9
                                                                                             LINENUMBER 269 L9
                                                                                             ALOAD 4
                                                                                             ICONST 1
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setTransactional (Z)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             L10
                                                                                             LINENUMBER 270 L10
                                                                                             ALOAD 4
                                                                                             ILOAD 3
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setAllowCreate (Z)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             L11
                                                                                             LINENUMBER 271 L11
                                                                                             ALOAD 4
                                                                                             ALOAD 0
                                                                                             GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.jeCacheSize: J
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setCacheSize (J)Lcom/sleepycat/je/EnvironmentMutableConfig;
                                                                                             POP
                                                                                             L12
                                                                                             LINENUMBER 272 L12
                                                                                             ALOAD 4
                                                                                             LDC "je.log.fileMax"
                                                                                             LDC 1000000000
                                                                                             INVOKESTATIC java/lang/String.valueOf (I)Ljava/lang/String;
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             L13
                                                                                             LINENUMBER 273 L13
                                                                                             ALOAD 4
                                                                                             LDC "com.sleepycat.je.util.FileHandler.level"
                                                                                             GETSTATIC com/sleepycat/analysis/MeasureDiskOrderedScan.FILELOGGINGLEVEL: Ljava/lang/String;
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
                                                                                             L14
                                                                                             LINENUMBER 274 L14
                                                                                             ALOAD 4
                                                                                             GETSTATIC com/sleepycat/analysis/MeasureDiskOrderedScan.LOCKING: Z
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setTxnSerializableIsolation (Z)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
                                                                                             L15
                                                                                             LINENUMBER 275 L15
                                                                                             ALOAD 4
                                                                                             GETSTATIC com/sleepycat/analysis/MeasureDiskOrderedScan.SHAREDCACHE : Z
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setSharedCache (Z)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
                                                                                             L16
                                                                                             LINENUMBER 278 L16
                                                                                             ALOAD 4
                                                                                             LDC "je.env.runEvictor"
                                                                                             LDC "false"
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
                                                                                             L17
                                                                                             LINENUMBER 279 L17
                                                                                             ALOAD 4
                                                                                             LDC "je.env.runOffHeapEvictor"
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             L18
                                                                                             LINENUMBER 280 L18
                                                                                             ALOAD 4
                                                                                             LDC "je.env.runINCompressor"
                                                                                             LDC "false"
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             L19
                                                                                             LINENUMBER 281 L19
LINENUMBER 260 L5
                                                                                             ALOAD 4
                                                                                             LDC "je.env.runCheckpointer" LDC "false"
NEW java/lang/IllegalArgumentException
NEW java/lang/StringBuilder
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
INVOKESPECIAL java/lang/StringBuilder.<init> ()V LDC "Must set heap size to at least internalMemoryLimit (if specified) plus 1.5 X jeCacheSize: "
                                                                                             L20
                                                                                             LINENUMBER 282 L20
INVOKEVIRTUAL java/lang/StringBuilder.append (Ljava/lang/String;)Ljava/lang/StringBuilder;
                                                                                             ALOAD 4
                                                                                             LDC "je.env.runCleaner"
LDC "false"
INVOKEVIRTUAL java/lang/StringBuilder.append (J)Ljava/lang/StringBuilder; INVOKEVIRTUAL java/lang/StringBuilder.toString ()Ljava/lang/String;
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
INVOKESPECIAL java/lang/IllegalArgumentException.<init> (Ljava/lang/String;)V
                                                                                             POP
ATHROW
                                                                                             L21
                                                                                             LINENUMBER 283 L21
                                                                                             ALOAD 4
                                                                                             LDC "je.env.runVerifier"
                                                                                             LDC "false"
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
                                                                                             L22
                                                                                             LINENUMBER 284 L22
                                                                                             ALOAD 4
                                                                                             LDC "je.stats.collect"
                                                                                             LDC "false"
                                                                                             INVOKEVIRTUAL com/sleepycat/je/EnvironmentConfig.setConfigParam (Ljava/lang/String;Ljava/lang/String;)Lcom/sleepycat/je/EnvironmentConfig;
                                                                                             POP
                                                                                             L23
                                                                                             LINENUMBER 287 L23
                                                                                             ALOAD 0
                                                                                             NEW com/sleepycat/je/Environment
                                                                                             NEW java/io/File
                                                                                             DUP
                                                                                             ALOAD 0
                                                                                             GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.homeDir : Ljava/lang/String; INVOKESPECIAL java/io/File.<init> (Ljava/lang/String;)V
                                                                                             ALOAD 4
                                                                                             INVOKESPECIAL com/sleepycat/je/Environment.<init> (Ljava/io/File;Lcom/sleepycat/je/EnvironmentConfig;)V PUTFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.env: Lcom/sleepycat/je/Environment;
                                                                                             L24
                                                                                             LINENUMBER 289 L24
                                                                                             NEW com/sleepycat/je/DatabaseConfig
                                                                                             INVOKESPECIAL com/sleepycat/je/DatabaseConfig.<init>()V
                                                                                             ASTORE 5
                                                                                             L25
                                                                                             LINENUMBER 290 L25
                                                                                             ALOAD 5
                                                                                             ILOAD 3
                                                                                             INVOKEVIRTUAL com/sleepycat/je/DatabaseConfig.setAllowCreate (Z)Lcom/sleepycat/je/DatabaseConfig;
                                                                                             L26
                                                                                             LINENUMBER 291 L26
                                                                                             ALOAD 5
                                                                                             ILOAD 3
                                                                                             INVOKEVIRTUAL com/sleepycat/je/DatabaseConfig.setExclusiveCreate (Z)Lcom/sleepycat/je/DatabaseConfig;
                                                                                             L27
                                                                                             LINENUMBER 292 L27
                                                                                             ALOAD 5
                                                                                             ALOAD 0
                                                                                             GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.dupDb: Z
                                                                                             INVOKEVIRTUAL com/sleepycat/je/DatabaseConfig.setSortedDuplicates (Z)Lcom/sleepycat/je/DatabaseConfig;
                                                                                             L28
                                                                                             LINENUMBER 293 L28
                                                                                             ALOAD 5
                                                                                             GETSTATIC com/sleepycat/je/CacheMode.EVICT_LN: Lcom/sleepycat/je/CacheMode; INVOKEVIRTUAL com/sleepycat/je/DatabaseConfig.setCacheMode (Lcom/sleepycat/je/CacheMode;)Lcom/sleepycat/je/DatabaseConfig;
                                                                                             POP
                                                                                             L29
                                                                                             LINENUMBER 294 L29
                                                                                             ALOAD 5
                                                                                             GETSTATIC com/sleepycat/analysis/MeasureDiskOrderedScan.REPLICATED: Z
                                                                                             INVOKEVIRTUAL com/sleepycat/je/DatabaseConfig.setReplicated (Z)Lcom/sleepycat/je/DatabaseConfig;
                                                                                             POP
                                                                                             L30
                                                                                             LINENUMBER 296 L30
                                                                                             ALOAD 0
                                                                                             ALOAD 0
                                                                                             GETFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.env: Lcom/sleepycat/je/Environment;
                                                                                             ACONST_NULL
                                                                                             LDC "foo"
                                                                                             ALOAD 5
                                                                                             INVOKEVIRTUAL com/sleepycat/je/Environment.openDatabase (Lcom/sleepycat/je/Transaction;Ljava/lang/String;Lcom/sleepycat/je/DatabaseConfig;)Lcom/sleepycat/je/Database;
                                                                                             PUTFIELD com/sleepycat/analysis/MeasureDiskOrderedScan.db: Lcom/sleepycat/je/Database;
                                                                                             LINENUMBER 297 L31
                                                                                             RETURN
                                                                                             L32
```

exit