L0 LINENUMBER 111 L0 LDC "f9a622de-c584-4f11-854d-f5973371cf9d" INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.enter (Ljava/lang/String;)V ALOAD 0 GETFIELD com/sleepycat/je/txn/LockImpl.firstWaiter: Lcom/sleepycat/je/txn/LockInfo; IFNULL L1 LINENUMBER 112 L2 ALOAD 0 GETFIELD com/sleepycat/je/txn/LockImpl.waiterList : Ljava/util/List; IFNONNULL L3 L4 LINENUMBER 113 L4 ALOAD 0 NEW java/util/ArrayList **DUP** INVOKESPECIAL java/util/ArrayList.<init>()V PUTFIELD com/sleepycat/je/txn/LockImpl.waiterList: Ljava/util/List; LINENUMBER 115 L3 FRAME SAME ALOAD 0 GETFIELD com/sleepycat/je/txn/LockImpl.waiterList : Ljava/util/List; ICONST\_0  $ALOAD\overline{0}$ GETFIELD com/sleepycat/je/txn/LockImpl.firstWaiter: Lcom/sleepycat/je/txn/LockInfo; INVOKEINTERFACE java/util/List.add (ILjava/lang/Object;)V LINENUMBER 118 L1 FRAME SAME ALOAD 0 ALOAD 1 PUTFIELD com/sleepycat/je/txn/LockImpl.firstWaiter: Lcom/sleepycat/je/txn/LockInfo; LINENUMBER 119 L5 ALOAD 2 GETSTATIC com/sleepycat/je/dbi/MemoryBudget.LOCKINFO\_OVERHEAD: I I2L ILOAD 3 L6 LINENUMBER 120 L6 INVOKEVIRTUAL com/sleepycat/je/dbi/MemoryBudget.updateLockMemoryUsage (JI)V

entry

exit

INVOKESTATIC edu/cmu/cs/mvelezce/java/execute/region/RegionsManager.exit (Ljava/lang/String;)V

LINENUMBER 121 L7

L8

LDC "f9a622de-c584-4f11-854d-f5973371cf9d"