

[Application Services](#) / ColorSync Manager

API Collection

# ColorSync Manager

## Overview

The ColorSync Manager is the API for ColorSync, a platform-independent color management system from Apple. ColorSync provides essential services for fast, consistent, and accurate color calibration, proofing, and reproduction using input, output, and display devices. ColorSync also provides an interface to system-wide color management settings that allows users to save color settings for specific jobs and switch between settings.

You need this reference if your software product performs color drawing, printing, or calculation, or if your peripheral device supports color. You also need this reference if you are creating a color management module (CMM)—a component that implements color-matching, color-conversion, and gamut-checking services.

The Color Picker Manager, documented separately, provides a standard user interface for soliciting color choices.

Carbon supports the majority of the ColorSync Manager programming interface. However, ColorSync 1.0 compatibility calls such as `CWNewColorWorld`, `GetProfile`, and `SetProfile` are not supported.

Nor does Carbon support ColorSync functions used for color management modules (CMMs). These functions aren't supported because macOS uses Bundle Services to implement CMMs.

Some applications use the Component Manager to determine what CMMs are available. You cannot use the Component Manager for this purpose in macOS. Apple has, however, provided the function `CMIterateCMMInfo` to query for available CMMs.

---

## Topics

# Working With Universal Procedure Pointers

**NewCMBitmapCallBackUPP**

Creates a new universal procedure pointer (UPP) to a bitmap callback.

**DisposeCMBitmapCallBackUPP**

Disposes of a universal procedure pointer (UPP) to a bitmap callback.

**InvokeCMBitmapCallBackUPP**

Invokes a universal procedure pointer (UPP) to a bitmap callback.

**NewCMConcatCallBackUPP**

Creates a new universal procedure pointer (UPP) to a progress-monitoring callback.

**DisposeCMConcatCallBackUPP**

Disposes of a universal procedure pointer (UPP) to a progress-monitoring callback.

**InvokeCMConcatCallBackUPP**

Invokes a universal procedure pointer (UPP) to a progress-monitoring callback.

**NewCMFlattenUPP**

Creates a new universal procedure pointer (UPP) to a data-flattening callback.

**DisposeCMFlattenUPP**

Disposes of a universal procedure pointer (UPP) to a data-flattening callback.

**InvokeCMFlattenUPP**

Invokes a universal procedure pointer (UPP) to a data-flattening callback.

**NewCMMIterateUPP**

Creates a new universal procedure pointer (UPP) to a progress-monitoring callback for the CMIterateCMMInfo function.

**DisposeCMMIterateUPP**

Disposes of a universal procedure pointer (UPP) to a progress-monitoring callback for the CMIterateCMMInfo function.

**InvokeCMMIterateUPP**

Invokes a universal procedure pointer (UPP) to a progress-monitoring callback for the CMIterateCMMInfo function.

## NewCMPProfileIterateUPP

Creates a new universal procedure pointer (UPP) to a profile-iteration callback.

## DisposeCMPProfileIterateUPP

Disposes of a universal procedure pointer (UPP) to a profile-iteration callback.

## InvokeCMPProfileIterateUPP

Invokes a universal procedure pointer (UPP) to a profile-iteration callback.

## Callbacks

### typealias CMFlattenProcPtr

Defines a pointer to a data transfer callback function that transfers profile data from the format for embedded profiles to disk file format or vice versa.

## Data Types

### struct CM2Profile

### struct CMDeviceInfo

### struct CMDeviceProfileArray

### struct CMDeviceScope

### struct CMError

Defines motion errors.

### typealias CMFlattenUPP

Defines a universal procedure pointer to a data-flattening callback.

### typealias CMMultiFunctLutA2BType

### struct CMMultiFunctLutType

### struct CMXYZColor

Contains values for a color specified in XYZ color space.

### typealias CMXYZComponent

## Constants

### ≡ Abstract Color Space Constants

Specify values that represent general color spaces.

⋮ Channel Encoding Format

Specify an encoding format for sRGB64.

⋮ Color Packing for Color Spaces

Specify how color values are stored.

⋮ Color Space Signatures

Define four-character-sequences associated with color spaces.

⋮ Color Space Masks

Specify masks used for color spaces.

⋮ Current Device Versions

Specify the current versions of the data structure containing information on registered devices.

⋮ Current Info Versions

Specify current device and profile versions.

⋮ Current Major Version Mask

Specifies the current major version number.

⋮ Data Transfer Commands

Specify commands for caller-supplied ColorSync data transfer functions.

⋮ Data Type Element Values

Specify a data type.

⋮ Default CMM Signature

Specifies a signature for the default color management module supplied by Color Sync.

⋮ Default IDs

Specify default values for device and profile IDs.

⋮ Device Attribute Values for Version 2.x Profiles

Define masks your application can use to set or test bits in the `deviceAttributes` field of the `CM2Header` structure.

`typealias CMDeviceClass`

Define constants to represent a variety of input and output devices.

### ☰ Device and Media Attributes

Used to set or obtain device or media attributes.

### ☰ Device States

Specify device states.

### ☰ Element Tags and Signatures for Version 1.0 Profiles

Define tags and signatures used for version 1.0 profiles.

### ☰ Embedded Profile Flags

Specify copyright-protection flag options,

### ☰ Flag Mask Definitions for Version 2.x Profiles

Define masks your application can use to set or test various bits in the `flags` field of the `CM2Header` structure.

### ☰ ICC Profile Versions

Specify IDD profile version numbers.

### ☰ Illuminant Measurement Endocings

Specify standard illuminate measurement encodings.

### ☰ Magic Cookie Number

Specifies a magic cookie number for anonymous file ID.

### ☰ Maximum Path Size

Specifies the maximum length for a path name.

### ☰ Measurement Flares

Specify measurement flare encodings.

### ☰ Measurement Geometries

Specify measurement geometry encodings.

### ☰ Parametric Types

Specify a parametric curve type enumeration,

### ☰ Platform Enumeration Values

Specify computer platforms.

### ☰ Profile Iteration Values

Specify profiles to iterate.

- ☰ Profile Location Sizes
  - Specify a location size.
- ☰ PostScript Data Formats
  - Specify constants that indicate the format of PostScript data.
- ☰ Profile Access Procedures
  - Specify operations used to access profiles.
- ☰ Profile Classes
  - Specify profile class enumerations.
- ☰ Profile Concatenation Values
  - Specify values to use when concatenating profiles.
- ☰ Profile Iteration Constants
  - Define an iteration version.
- ☰ Profile Location Type
  - Defines profile location kinds.
- ☰ Public Tags
  - Specify tag values available for public use.
- ☰ Public Type Signatures
  - Specify signatures for public types.
- ☰ Quality Flag Values for Version 2.x Profiles
  - Define the possible values for the quality bits in the `flags` field of the `CM2Header` structure.
- ☰ Rendering Intent Values for Version 2.x Profiles
  - Define the four possible values for the rendering intent bits of the `renderingIntent` field of the `CM2Header` structure.
- ☰ Screen Encoding Tags
  - Specify tags to use for screen encodings.
- ☰ Spot Function Values
  - Specify values for spot functions.
- ☰ Standard Observer
  - Standard observer measurement type encodings.

⋮ Tag Type Information  
Defines a constant for 2.0 tag type information.

⋮ Technology Tag Descriptions  
Define descriptor tags for technologies.

⋮ Use Types  
Specify use types.

⋮ Video Card Gamma Storage Types  
Specify data storage type constants.

⋮ Video Card Gamma Tags  
Specify video card gamma information.

⋮ Video Card Gamma Signatures  
Specify signatures used for video card gamma information.

## Result Codes

The most common result codes returned by ColorSync Manager are listed below.

var cmProfileError: Int  
There is something wrong with the content of the profile

var cmMethodError: Int  
An error occurred during the CMM arbitration process that determines the CMM to use

var cmMethodNotFound: Int  
CMM not present

var cmProfileNotFound: Int  
Responder error

var cmProfilesIdentical: Int  
Profiles are the same

var cmCantConcatenateError: Int  
Profiles cannot be concatenated

var cmCantXYZ: Int  
CMM does not handle XYZ color space

```
var cmCantDeleteProfile: Int
    Responder error

var cmUnsupportedDataType: Int
    Responder error

var cmNoCurrentProfile: Int
    Responder error

var cmElementTagNotFound: Int
    The tag you specified is not in the specified profile

var cmIndexRangeErr: Int
    Tag index out of range

var cmCantDeleteElement: Int
    Cannot delete the specified profile element

var cmFatalProfileErr: Int
    Returned from File Manager while updating a profile file in response to CMUpdateProfile;
    profile content may be corrupted

var cmInvalidProfile: Int
    Profile reference is invalid or refers to an inappropriate profile

var cmInvalidProfileLocation: Int
    Operation not supported for this profile location

var cmInvalidSearch: Int
    Bad search handle

var cmSearchError: Int
    Internal error occurred during profile search

var cmErrIncompatibleProfile: Int
    Unspecified profile error

var cmInvalidColorSpace: Int
    Profile color space does not match bitmap type

var cmInvalidSrcMap: Int
    Source pixel map or bitmap was invalid
```

```
var cmInvalidDstMap: Int
    Destination pix/bit map was invalid

var cmNoGDevicesError: Int
    Begin matching or end matching—no graphics devices available

var cmInvalidProfileComment: Int
    Bad profile comment during drawpicture

var cmRangeOverFlow: Int
    One or more output color value overflows in color conversion; all input color values will be converted and the overflow will be clipped

var cmCantCopyModifiedV1Profile: Int
    It is illegal to copy version 1.0 profiles that have been modified

var cmNamedColorNotFound: Int
    The specified named color was not found in the specified profile

var cmCantGamutCheckError: Int
    Gamut checking not supported by this color world—that is, the color world does not contain a gamut table because it was built with gamut checking turned off

var cmDeviceDBNotFoundErr: Int
    Preferences not found or loaded; returned by a CM device integration routine.

var cmDeviceAlreadyRegistered: Int
    Device already registered; returned by a CM device integration routine.

var cmDeviceNotRegistered: Int
    Device not found; returned by a CM device integration routine.

var cmDeviceProfilesNotFound: Int
    Profiles not found; returned by a CM device integration routine.

var cmInternalCFErr: Int
    CoreFoundation failure; returned by a CM device integration routine.
```

---

## See Also

## Managers

☰ Apple Event Manager

☰ Speech Synthesis Manager