Task-4

Setup and Use a Firewall on Windows/Linux

```
See 'snap info <snapname>' for additional versions.
┌──(hacker㉿hacker)-[~]
└─$ sudo su
┌──(root㉿hacker)-[/home/hacker]
└─# ufw default deny incoming
Default incoming policy changed to 'deny'
(be sure to update your rules accordingly)
┌──(root㉿hacker)-[/home/hacker]
└─# ufw default deny outgoing
Default outgoing policy changed to 'deny'
(be sure to update your rules accordingly)
┌──(root㉿hacker)-[/home/hacker]
└─# systemctl status ufw
○ ufw.service - Uncomplicated firewall
     Loaded: loaded (/usr/lib/systemd/system/ufw.service; enabled; preset: enabled)
     Active: inactive (dead)
       Docs: man:ufw(8)
┌──(root㉿hacker)-[/home/hacker]
└─# systemctl status ufw
○ ufw.service - Uncomplicated firewall
     Loaded: loaded (/usr/lib/systemd/system/ufw.service; enabled; preset: enabled)
     Active: inactive (dead)
       Docs: man:ufw(8)
┌──(root㉿hacker)-[/home/hacker]
└─# ufw status
Status: inactive
┌──(root㉿hacker)-[/home/hacker]
└─# sudo ufw allow ssh
Rules updated
Rules updated (v6)
┌──(root㉿hacker)-[/home/hacker]
└─# sudo ufw allow http
Rules updated
Rules updated (v6)
┌──(root㉿hacker)-[/home/hacker]
└─# sudo ufw allow ftp
Rules updated
Rules updated (v6)
```

```
File  Actions  Edit  View  Help
└─# sudo ufw allow ssh
Rules updated
Rules updated (v6)
┌──(root㉿hacker)-[/home/hacker]
└─# sudo ufw allow http
Rules updated
Rules updated (v6)
┌──(root㉿hacker)-[/home/hacker]
└─# sudo ufw allow ftp
Rules updated
Rules updated (v6)
┌──(root㉿hacker)-[/home/hacker]
└─# ufw allow from 10.0.0.1
Rules updated
┌──(root㉿hacker)-[/home/hacker]
└─# ufw allow from 10.0.0.1 to any port 22
Rules updated
┌──(root㉿hacker)-[/home/hacker]
└─# systemctl start ufw
┌──(root㉿hacker)-[/home/hacker]
└─# ufw enable
Firewall is active and enabled on system startup
┌──(root㉿hacker)-[/home/hacker]
└─# ufw status
Status: active

To                         Action      From
--                         ------      ----
22/tcp                     ALLOW       Anywhere
80/tcp                     ALLOW       Anywhere
21/tcp                     ALLOW       Anywhere
Anywhere                   ALLOW       10.0.0.1
22                         ALLOW       10.0.0.1
22/tcp (v6)                ALLOW       Anywhere (v6)
80/tcp (v6)                ALLOW       Anywhere (v6)
21/tcp (v6)                ALLOW       Anywhere (v6)
```