Filserver - PepeLaughSrv1

Location

PepeLaugh Office, PogChampStreet 76

Hardware

- Processor: 2x AMD EPYC[™] 72F3 Processor 8-core 3.70GHz 256MB Cache (180W)
- RAM: 8x 16GB PC4-23400 2933MHz DDR4 ECC RDIMM
- Boot drive: 960GB Micron 5400 PRO Series 2.5" SATA 6.0Gb/s Solid State Drive
- Storage drives: 12x 10TB SAS 3.0 12.0Gb/s 7200RPM 3.5" Ultrastar™ DC HC330 (512e)
 - For more hardware info see FileServerSpecs.pdf

Configuration

- OS: Windows Server 2022 Server Standard
- Build: 21H2 20348.169
- Display Resolution: 1024x768

Network Configuration:

- IP adress 10.6.68.177
- Subnet mask: 255.255.255
- Default gateway 10.6.68.1
- Preferred DNS server: 10.6.68.175
- Alternate DNS server: None

Storage Services

- Storage Pool 1
 - Name: RAID5
 - Physical Disks: 12x 10TB

Roles and Features

Print Server

Shared Folders

\PepeLaughSrv1\Private\$

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files

- Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
- Creator Owner (Allow)
 - Full Control
 - Subfolders and fils only
- Domain users (Allow)
 - Traverse folder / execute file
 - List folder / read data
 - Create folders / append data
 - This folder only
- PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
- PepeLaughAccounting (Allow)
 - Read, write & execute
 - This folder, subfolders and files
- PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files
- PepeLaughSales (Allow)
 - Read, write & execute
 - This folder, subfolders and files
- PepeLaughConsultant (Allow)
 - Read, write & execute
 - This folder, subfolders and files

\PepeLaughSrv1\PepeLaughShared

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files
 - Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
 - Creator Owner (Allow)
 - Full Control
 - Subfolders and fils only
 - PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
 - PepeLaughAccounting (Allow)
 - Read, write & execute
 - This folder, subfolders and files

- PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files
- PepeLaughSales (Allow)
 - Read, write & execute
 - This folder, subfolders and files
- PepeLaughConsultant (Allow)
 - Read, write & execute
 - This folder, subfolders and files

\PepeLaughSrv1\PepeLaughAccounting

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files
 - Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
 - Creator Owner (Allow)
 - Full Control
 - Subfolders and fils only
 - PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
 - PepeLaughAccounting (Allow)
 - Read, write & execute
 - This folder, subfolders and files
 - PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files

\PepeLaughSrv1\PepeLaughConsultant

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files
 - Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
 - Creator Owner (Allow)
 - Full Control

- Subfolders and fils only
- PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
- PepeLaughConsultant (Allow)
 - Read, write & execute
 - This folder, subfolders and files
- PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files

\PepeLaughSrv1\PepeLaughSales

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files
 - Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
 - Creator Owner (Allow)
 - Full Control
 - Subfolders and fils only
 - PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
 - PepeLaughSales (Allow)
 - Read, write & execute
 - This folder, subfolders and files
 - PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files

\PepeLaughSrv1\PepeLaughManagement

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files
 - Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
 - Creator Owner (Allow)

- Full Control
- Subfolders and fils only
- PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
- PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files

\PepeLaughSrv1\PepeLaughIT

- Share Permissions:
 - Authenticated Users: Full Control
- NTFS Permissions:
 - System (Allow)
 - Full Control
 - This folder, subfolders and files
 - Administrators (Allow)
 - Full Control
 - This folder, subfolders and files
 - Creator Owner (Allow)
 - Full Control
 - Subfolders and fils only
 - PepeLaughIT (Allow)
 - Full Control
 - This folder, subfolders and files
 - PepeLaughManagement (Allow)
 - Read, write & execute
 - This folder, subfolders and files

Mapped Drives

- 1. PepeLaughAccounting
- Folder: \PepeLaughSrv1\PepeLaughAccounting
- Mount as Network Drive
- Drive letter: First available from I:
- Item Level Targeting:
 - o (Security Group) PepeLaughAccounting
 - o OR (Security Group) PepeLaughManagement
 - o OR (Security Group) PepeLaughIT
- 2. PepeLaughConsultant
- Folder: \PepeLaughSrv1\PepeLaughConsultant
- Mount as Network Drive
- Drive letter: First available from I:
 - Item Level Targeting:

- o (Security Group) PepeLaughConsultant
- o OR (Security Group) PepeLaughManagement
- o OR (Security Group) PepeLaughIT

3. PepeLaughSales

- Folder: \PepeLaughSrv1\PepeLaughSales
- Mount as Network Drive
- Drive letter: First available from I:
- Item Level Targeting:
 - (Security Group) PepeLaughSales
 - o OR (Security Group) PepeLaughManagement
 - o OR (Security Group) PepeLaughIT

4. PepeLaughManagement

- Folder: \PepeLaughSrv1\PepeLaughManagement
- Mount as Network Drive
- Drive letter: First available from I:
- Item Level Targeting:
 - o (Security Group) PepeLaughSales
 - OR (Security Group) PepeLaughManagement
 - o OR (Security Group) PepeLaughIT

5. PepeLaughIT

- Folder: \PepeLaughSrv1\PepeLaughIT
- Mount as Network Drive
- Drive letter: First available from I:
- Item Level Targeting:
 - (Security Group) PepeLaughSales
 - o OR (Security Group) PepeLaughManagement
 - OR (Security Group) PepeLaughIT

1. PepeLaughShared

- Folder: \PepeLaughSrv1\PepeLaughShared
- Mount as Network Drive
- Drive letter: First available from S:
- Item Level Targeting: (Security Group) PepeLaughAccounting OR (Security Group)
 PepeLaughConsultant OR (Security Group) PepeLaughSales OR (Security Group)
 PepeLaughManagement OR (Security Group) PepeLaughIT

Printers

- 1. PepeLaughPrinter
- IP: 10.6.68.179
- Deploy with GPO Per Machine to respective OU
- Driver: Microsoft OpenXPS Class Driver 2

- Noteable Permissions:
 - Allow PepeLaughEmployees: Print
 - o Allow PepeLaughIT: Print, Manage this printer, Manage documents
 - Allow Creator Owner: Manage documents